



Microsoft Dynamics® GP
Fixed Assets Management

Copyright

Copyright © 2011 Microsoft. All rights reserved.

Limitation of liability

This document is provided "as-is." Information and views expressed in this document, including URL and other Internet Web site references, may change without notice. You bear the risk of using it.

Some examples depicted herein are provided for illustration only and are fictitious. No real association or connection is intended or should be inferred.

Intellectual property

This document does not provide you with any legal rights to any intellectual property in any Microsoft product.

You may copy and use this document for your internal, reference purposes.

Trademarks

Microsoft, Excel, and Microsoft Dynamics are trademarks of the Microsoft group of companies. FairCom and c-tree Plus are trademarks of FairCom Corporation and are registered in the United States and other countries.

All other trademarks are property of their respective owners.

Warranty disclaimer

Microsoft Corporation disclaims any warranty regarding the sample code contained in this documentation, including the warranties of merchantability and fitness for a particular purpose.

License agreement

Use of this product is covered by a license agreement provided with the software product. If you have any questions, please call the Microsoft Dynamics GP Customer Assistance Department at 800-456-0025 (in the U.S. or Canada) or +1-701-281-6500.

Publication date

April 2011

Contents

Introduction	2
What's in this manual.....	2
Symbols and conventions	3
Resources available from the Help menu.....	3
Send us your documentation comments	5
Part 1: Fixed Asset Management setup	8
Chapter 1: Fixed Asset Management setup	9
Integration with other modules	9
Before you set up Fixed Asset Management.....	11
Setting up Fixed Asset Management	11
Building the Fixed Asset Management fiscal calendar	11
Rebuilding the fiscal calendar.....	12
Verifying a fiscal calendar year	13
Setting up quarter records	13
Synchronizing quarter records.....	14
Creating a book record	14
Creating a class record	16
Depreciation methods and calculations	17
Amortization codes.....	19
Averaging conventions	19
Creating a book class record.....	21
Chapter 2: Company setup options	23
Asset account option	23
Asset book options.....	23
User data options	23
Purchasing integration options.....	24
Fixed assets purchasing transactions	24
Setting up company records.....	25
Chapter 3: Optional setup procedures	27
Account groups	27
Creating an account group	28
Entering fixed assets posting accounts	29
Setting up an insurance class record	30
Creating a lease company record.....	31
Creating a location record.....	31
Creating a physical location record.....	32
Creating a retirement code	33
Creating a structure ID.....	33
Setting up user preferences	34
Setting up user-defined field values	35

Part 2: Cards and integration	38
Chapter 4: Fixed Asset Management cards	39
Creating an asset record.....	39
Adding asset records from other modules.....	42
Modifying an asset account record.....	42
Class IDs and account groups.....	42
Creating an asset book record.....	43
Chapter 5: Additional Fixed Asset Management cards	45
Using Section 179 Expense Deduction.....	45
Creating an asset book ITC record.....	46
Adjusting the cost basis to equal the net cost basis.....	47
Creating an asset insurance record.....	47
Creating an asset lease record.....	48
Creating an asset user-defined record.....	48
Chapter 6: Integration	51
Using Fixed Asset Management with Payables Management.....	51
Adding asset records from Payables Management.....	52
Using Fixed Asset Management with Purchase Order Processing.....	54
Integration options for Purchase Order Processing.....	55
Adding asset records from Purchase Order Processing—by Account option.....	55
Adding asset information after receiving purchasing transactions.....	57
Adding asset records from Purchase Order Processing—by Receipt Line option.....	58
Using Fixed Asset Management with Multicurrency Management.....	61
Chapter 7: Asset import	63
Guidelines for importing asset information.....	63
Importing asset records.....	64
Creating a new book record for existing assets.....	65
Field mappings for importing asset information.....	66
Field values.....	71
Part 3: Asset records	74
Chapter 8: Asset groups	75
Searching for assets.....	75
Building an asset group.....	75
Viewing assets in groups.....	77
Importing data to create an asset group.....	77
Deleting an asset group.....	78
Removing assets from a group.....	78
Chapter 9: Asset maintenance	79
Changing asset information.....	79
Recalculating depreciation.....	80
Changing information for a group of assets.....	81
Deleting an asset book record.....	82

Calculating mid-quarter depreciation	83
Chapter 10: Asset transfer.....	85
Transferring asset record information.....	85
Partially transferring an asset	86
Transferring multiple assets	87
Chapter 11: Asset retirement.....	89
Retirement proceeds and expenses	89
Recording the sale or disposal of an asset.....	90
Partially retiring an asset	90
Reversing a retired asset record	92
Using retirement spread options	92
Recording the sale or retirement of a group of assets.....	94
Chapter 12: Asset depreciation.....	95
Depreciating one asset.....	95
Depreciating assets in one or more books.....	96
Recalculating depreciation for an asset	97
Reversing depreciation for an asset	97
Projecting depreciation for one asset	98
Projecting depreciation for assets in one or more books.....	98
Part 4: Routines	102
Chapter 13: Year-end processes	103
Closing the asset books	104
Summarizing financial data	105
Deleting inactive asset information.....	105
Chapter 14: General Ledger integration.....	107
Migrating from another fixed assets system.....	107
Updating General Ledger with Fixed Asset Management transactions.....	108
Asset records—Require Account option	109
Reprinting the FA Posting to General Ledger report.....	109
Rebuilding integrated batches	109
Chapter 15: Physical inventory	111
Importing physical location IDs for existing assets	111
Creating an asset labels file	112
Reconciling physical locations for assets.....	112
Part 5: Utilities and detail file activity	116
Chapter 16: Table maintenance.....	117
Reconciling asset information.....	117
Deleting an asset	118
Deleting fixed assets purchasing transactions.....	119
Chapter 17: Financial detail file activity.....	121

Activity table abbreviations and descriptions	121
Activity table for adding a record	122
Activity table for changing a record.....	122
Activity table for mass changes to records.....	124
Activity table for deleting a record.....	125
Activity table for depreciating a record.....	125
Activity detail for transferring a record.....	126
Activity table for mass transfer of records	127
Activity table for retiring a record.....	127
Activity detail for mass retiring records.....	128
Activity detail for unretiring records	129
Part 6: Inquiries and reports	132
Chapter 18: Inquiries	133
Viewing asset information	133
Viewing asset book information	135
Comparing asset books	136
Viewing financial detail information	137
Viewing asset retirement information	138
Viewing the error log.....	139
Viewing transfer information.....	139
Viewing projected depreciation information	140
Viewing purchasing transactions information	141
General Ledger inquiries	142
Chapter 19: Reports	143
Fixed Asset Management reports summary	143
Report destinations and formats	146
Processing reports on a process server	147
Creating report options	147
Printing a report with an option.....	148
Customizing a report.....	148
Fixed Asset Management Microsoft SQL® Server Reporting Services reports.....	149
Glossary	151
Index.....	153

Introduction

You can use Fixed Asset Management, to set up, enter, and maintain asset records. When necessary, you can add insurance and user-defined information and create additional records for each asset, including investment tax credit information and lease information.

You also can use Fixed Asset Management to complete the following tasks:

- Calculate depreciation
- Import information to Fixed Asset Management from other sources
- Create and use asset groups to make maintaining asset records easier
- Transfer an asset to a new general ledger account or property tax location
- Retire an asset, partially retire an asset, or retire a group of assets

If you're using General Ledger, you can track General Ledger information entered in Fixed Asset Management, such as additions, transfers, depreciation, retirement of assets, and other changes.

If you're using Payables Management or Purchase Order Processing, you can track assets that originate in those modules and add them as fixed assets.

This introduction is divided into the following sections:

- [*What's in this manual*](#)
- [*Symbols and conventions*](#)
- [*Resources available from the Help menu*](#)
- [*Send us your documentation comments*](#)

What's in this manual

This manual is designed to give you an understanding of how to use the features of Fixed Asset Management, and how it integrates with the Microsoft Dynamics® GP system.

To make best use of Fixed Asset Management, you should be familiar with systemwide features described in the System User's Guide, the System Setup Guide, and the System Administrator's Guide.

Some features described in the documentation are optional and can be purchased through your Microsoft Dynamics GP partner.

To view information about the release of Microsoft Dynamics GP that you're using and which modules or features you are registered to use, choose Help >> About Microsoft Dynamics GP.



The manual is divided into the following parts:

- [**Part 1, Fixed Asset Management setup**](#), provides information about setting up your Fixed Asset Management system.
- [**Part 2, Cards and integration**](#), provides information about asset records. It also explains how to import information from other sources and how Fixed Asset Management integrates with other Microsoft Dynamics GP modules.

- [Part 3, Asset records](#), provides information about maintaining asset information. It also explains how to use asset groups to make maintaining asset records easier.
- [Part 4, Routines](#), provides information about procedures you can use to calculate depreciation and integrate Fixed Asset Management with General Ledger.
- [Part 5, Utilities and detail file activity](#), provides information about maintaining the integrity of your Fixed Asset Management data by reconciling your records and performing maintenance on the Fixed Asset Management data tables.
- [Part 6, Inquiries and reports](#), provides information about viewing and printing Fixed Asset Management data and analyzing asset activity by printing specific reports. It also lists the financial information relating to the many activities that can occur within Fixed Asset Management.

Symbols and conventions

For definitions of unfamiliar terms, see the glossary in the manual or refer to the glossary in Help.

Symbol	Description
	The light bulb symbol indicates helpful tips, shortcuts and suggestions.
	The warning symbol indicates situations you should be especially aware of when completing tasks.

This manual uses the following conventions to refer to sections, navigation and other information.

Convention	Description
<i>Creating a batch</i>	Italicized type indicates the name of a section or procedure.
File >> Print or File > Print	The (>>) or (>) symbol indicates a sequence of actions, such as selecting items from a menu or toolbar, or pressing buttons in a window. This example directs you to go to the File menu and choose Print.
TAB or ENTER	All capital letters indicate a key or a key sequence.

Resources available from the Help menu

The Microsoft Dynamics GP Help menu gives you access to user assistance resources on your computer, as well as on the Web.

Contents

Opens the Help file for the active Microsoft Dynamics GP component, and displays the main “contents” topic. To browse a more detailed table of contents, click the Contents tab above the Help navigation pane. Items in the contents topic and tab are arranged by module. If the contents for the active component includes an “Additional Help files” topic, click the links to view separate Help files that describe additional components.

To find information in Help by using the index or full-text search, click the appropriate tab above the navigation pane, and type the keyword to find.

To save the link to a topic in the Help, select a topic and then select the Favorites tab. Click Add.

Index

Opens the Help file for the active Microsoft Dynamics GP component, with the Index tab active. To find information about a window that's not currently displayed, type the name of the window, and click Display.

About this window

Displays overview information about the current window. To view related topics and descriptions of the fields, buttons, and menus for the window, choose the appropriate link in the topic. You also can press F1 to display Help about the current window.

Lookup

Opens a lookup window, if a window that you are viewing has a lookup window. For example, if the Checkbook Maintenance window is open, you can choose this item to open the Checkbooks lookup window.

Show Required Fields

Highlights fields that are required to have entries. Required fields must contain information before you can save the record and close the window. You can change the font color and style used to highlight required fields. On the Microsoft Dynamics GP menu, choose User Preferences, and then choose Display.

Printable Manuals

Displays a list of manuals in Adobe Acrobat .pdf format, which you can print or view.

What's New

Provides information about enhancements that were added to Microsoft Dynamics GP since the last major release.

Microsoft Dynamics GP Online

Opens a Web page that provides links to a variety of Web-based user assistance resources. Access to some items requires registration for a paid support plan.

Current implementation and upgrade information The most recent revisions of upgrade and implementation documentation, plus documentation for service packs and payroll tax updates.

User documentation and resources The most recent user guides, how-to articles, and white papers for users.

Developer documentation and resources The most recent documentation and updated information for developers.

Product support information Information about the Microsoft Dynamics GP product support plans and options that are available, along with information about peer support and self-support resources.

Services information Information about Microsoft Dynamics GP support, training, and consulting services.

Microsoft Dynamics GP Community Access to newsgroups, where you can ask questions or share your expertise with other Microsoft Dynamics GP users.

CustomerSource home page A wide range of resources available to customers who are registered for a paid support plan. Includes access to Knowledge Base articles, software downloads, self-support, and much more.

Customer Feedback Options

Provides information about how you can join the Customer Experience Improvement Program to improve the quality, reliability, and performance of Microsoft® software and services.

Send us your documentation comments

We welcome comments regarding the usefulness of the Microsoft Dynamics GP documentation. If you have specific suggestions or find any errors in this manual, send your comments by e-mail to the following address: bizdoc@microsoft.com.

To send comments about specific topics from within Help, click the Documentation Feedback link, which is located at the bottom of each Help topic.

Note: By offering any suggestions to Microsoft, you give Microsoft full permission to use them freely.

Part 1: Fixed Asset Management setup

This part of the documentation provides information about setting up your Fixed Asset Management system.

This part includes the following information:

- [Chapter 1, "Fixed Asset Management setup,"](#) describes how to set up default options and information for Fixed Asset Management. It also describes how to set up the Fixed Asset Management fiscal calendar and asset books and classes.
- [Chapter 2, "Company setup options,"](#) explains how to set up user-defined fields and additional information to use if your system is integrated with Purchase Order Processing or Payables Management.
- [Chapter 3, "Optional setup procedures,"](#) explains how to set up account groups, posting accounts, insurance classes, lease company records, and location records.

Chapter 1: Fixed Asset Management setup

The default options and information that you enter before adding fixed assets records to your system will ensure that information will be available when you set up fixed asset cards. You should first set up the Fixed Assets Fiscal Calendar and quarters. You can then set up book, class, book class, and company records.

The following information is discussed:

- [*Integration with other modules*](#)
- [*Before you set up Fixed Asset Management*](#)
- [*Setting up Fixed Asset Management*](#)
- [*Building the Fixed Asset Management fiscal calendar*](#)
- [*Rebuilding the fiscal calendar*](#)
- [*Verifying a fiscal calendar year*](#)
- [*Setting up quarter records*](#)
- [*Synchronizing quarter records*](#)
- [*Creating a book record*](#)
- [*Creating a class record*](#)
- [*Depreciation methods and calculations*](#)
- [*Amortization codes*](#)
- [*Averaging conventions*](#)
- [*Creating a book class record*](#)

After you've completed a setup procedure, you can choose File >> Print to print the setup record and verify the information.

Integration with other modules

Use Fixed Asset Management to enter information about your company's assets, such as insurance records, depreciation amount, retirements, lease information, repairs, and maintenance.


The only Microsoft Dynamics GP module you're required to use with Fixed Asset Management is System Manager. Fixed Asset Management does integrate with other modules, which, if registered, provide additional functionality to your system.

General Ledger integration If you're also using General Ledger, all Fixed Asset Management transactions that affect financial information will be reflected in General Ledger.

Payables Management integration If you're also using Payables Management, transactions that are recorded in Payables Management can update your asset records.

Purchase Order Processing integration If you're also using Purchase Order Processing, transactions that are recorded in Purchase Order Processing can update your asset records.

The following diagram shows how information flows through Fixed Asset Management.



Before you set up Fixed Asset Management

Before you can set up Fixed Asset Management, you should have completed the following company setup procedures:

- Set up account formats
- Set up fiscal periods
- Set up a chart of accounts

If you haven't completed each of the preceding tasks, do so before continuing. Refer to the System Setup documentation for more information.

Setting up Fixed Asset Management

You must set up the fiscal calendar and quarter, book, class, book class and company records before you can use Fixed Asset Management. The following table provides a list of records you must set up:

To set up	Refer to
Fiscal calendar records	Building the Fixed Asset Management fiscal calendar on page 11.
Quarter records	Setting up quarter records on page 13.
Book records	Creating a book record on page 14.
Class records	Creating a class record on page 16.
Book class records	Creating a book class record on page 21.
Company records	Setting up company records on page 25.

After you've entered calendar, quarter, book, class, book class, and company records, you should complete the following procedures.

Procedure	Additional information
Create or import asset records.	Refer to Creating an asset record on page 39 or Importing asset records on page 64.
Print reports to verify that information was entered correctly.	You can print the Depreciation Ledger, Depreciation Detail Report, and the Property Ledger.
Integrate Fixed Asset Management data with General Ledger.	Refer to Updating General Ledger with Fixed Asset Management transactions on page 108.

Building the Fixed Asset Management fiscal calendar

You can build the Fixed Assets Fiscal Calendar from the Fiscal Period table used by the other modules in your financial system. However, only Fixed Asset Management uses the Fixed Assets Fiscal Calendar tables.


Before you build the Fixed Asset Management calendar, be sure that there is at least one fiscal year set up in your system and that the years and periods in the Fiscal Period Setup window are correct. The information in the Fiscal Period Setup window is used to create fiscal periods for other years in the Fixed Asset Management fiscal calendar.

Use the Build Fixed Assets Calendar window to build the fiscal calendar and to set up quarter records for each year in the Fixed Asset Management fiscal calendar.

For more information about setting up fiscal periods, refer to online help for the Fiscal Periods Setup window.

To build the Fixed Asset Management fiscal calendar:

1. Open the Build Fixed Assets Fiscal Calendar window.
(Microsoft Dynamics GP menu >> Tools >> Utilities >> Fixed Assets >> Build Calendar)



2. Mark the Build Fixed Assets Fiscal Calendar option.

Fixed Asset Management builds fiscal periods for 100 years prior to and 200 years after the year 2000, so the default range of years is 1901 to 2199. We recommend that you accept the default years when you build the Fixed Assets Fiscal Calendar.



Mark the Replace option only if you are rebuilding the file. If you mark this option, all Fixed Asset Management Fiscal Calendar tables will be deleted before the new range of years is created. To rebuild the fiscal calendar, see [Rebuilding the fiscal calendar](#) on page 12.

3. Choose Build.

Rebuilding the fiscal calendar

Use the Build Fixed Assets Fiscal Calendar window to rebuild the Fixed Asset Management fiscal calendar. You should rebuild the fiscal calendar when you add additional fiscal years in the Fiscal Periods Setup window. The existing fiscal calendar table will be deleted and replaced with new fiscal year information.

To rebuild the fiscal calendar:


1. Open the Build Fixed Assets Fiscal Calendar window.
(Microsoft Dynamics GP menu >> Tools >> Utilities >> Fixed Assets >> Build Calendar)
2. Mark the Build Fixed Assets Fiscal Calendar option and the Replace option.
3. Choose Build.

Verifying a fiscal calendar year

Use the Fiscal Period Inquiry window to verify that no gaps in dates exist in any years included in the Fixed Asset Management fiscal calendar.

To verify a fiscal calendar year:

1. Open the Build Fixed Assets Fiscal Calendar window.
(Microsoft Dynamics GP menu >> Tools >> Utilities >> Fixed Assets >> Build Calendar)
2. Choose Inquire to open the Fiscal Period Inquiry window.



3. Choose Verify to verify the fiscal periods in the Fixed Assets Fiscal Calendar and to print the Fixed Assets Fiscal Calendar Verify report.


Setting up quarter records

You can set up quarter records to specify starting, ending, and middle dates of each quarter in a year, any time after you've built the Fixed Asset Management fiscal calendar. You must enter at least one year and define quarter setup records for each year if you use the mid-quarter averaging for calculating depreciation or transfer groups of assets.

Use the Quarter Setup window to set up quarter records and then use the Build Fixed Assets Calendar window to synchronize the records. The year you enter in the Quarter Setup window will be used to build quarters for each year in the Fixed Assets Fiscal Calendar table.

To set up quarter records:

1. Open the Quarter Setup window.
(Microsoft Dynamics GP menu >> Tools >> Setup >> Fixed Assets >> Quarter)



2. Select a year. The year you enter must be defined in the Fixed Assets Fiscal Calendar table.
3. Select a quarter.
4. Enter the starting and ending dates of the quarter.
5. Enter or accept the mid-date of the quarter. The middle date will be calculated, but you can change it.
6. Choose Save.
7. Repeat steps 3 through 6 to define remaining quarters for a year.

Synchronizing quarter records

After you've set up quarter records using the Quarter Setup window, use the Build Fixed Assets Calendar window to synchronize quarters to fiscal years.

To synchronize quarter records:

1. Open the Build Fixed Assets Fiscal Calendar window.
(Microsoft Dynamics GP menu >> Tools >> Utilities >> Fixed Assets >> Build Calendar).
2. Mark the Synchronize Quarters to Fiscal Years option to add quarters for all the fiscal years in the Fixed Assets Fiscal Calendar table.
3. Choose Build to synchronize quarters to fiscal years.

Creating a book record


Use the Book Setup window to define the books you'll use for fixed assets reporting. For example, you can create a book for corporate reporting, earnings and profits, federal taxes, alternative minimum tax, state tax, or for any other of your company's accounting needs. You can set up an unlimited number of books for each company.

When you initially create a book record, you must select the current fiscal year, and the year must be a valid year in the Fixed Asset Management fiscal calendar. The year determines whether depreciation expense will be posted to the current depreciation expense account or to the prior year depreciation account. Each time you complete year-end processing for a book, the year will be updated.

To see differences between the depreciation calculated using internal book rules and tax book rules, you can compare up to three books. For more information, refer to [Comparing asset books](#) on page 136.

To create a book record:

1. Open the Book Setup window.
(Microsoft Dynamics GP menu >> Tools >> Setup >> Fixed Assets >> Book)



2. Enter a book ID and description.
3. Select the current fiscal year.
4. Select a period to determine how the yearly depreciation amount will be allocated.

Periodically To the number of periods in the year.

Daily To the number of days in the year.

5. Mark Auto Add Book Info to add an asset book record to this book when you add an asset using the Asset General Information window.
6. Mark the Post to General Ledger option to post all transactions associated with the selected book ID to General Ledger. This option is available only if you have marked the Allow Reporting ledger in the Fixed Assets Company setup window (Microsoft Dynamics GP menu >> Tools >> Setup >> Fixed Assets >> Company).



When you mark the Allow Reporting Ledger option in the Fixed Assets Company Setup window, the Post to General Ledger option will be automatically marked and unavailable for selection for the corporate book.

7. Select the Reporting Ledger, Base, IFRS or Local, to report all transactions associated with the book ID. This option is available only if you have marked the Allow Reporting ledger in the Fixed Assets Company setup window (Microsoft Dynamics GP menu >> Tools >> Setup >> Fixed Assets >> Company).

When you mark the Allow Reporting Ledger option in the Fixed Assets Company Setup window, BASE will be selected as the reporting ledger automatically for the corporate book.



Any corporate book transactions completed prior to marking the Allow Reporting Ledgers option in the Fixed Assets Company Setup window (Microsoft Dynamics GP menu >> Tools >> Setup >> Fixed Assets >> Company) will be automatically assigned

to the BASE reporting ledger in General Ledger. If you change the assigned reporting ledger in the Book Setup window, you may want to correct the transactions that already exist in General Ledger for that book.

8. Choose Save.

Creating a class record

Use the Class Setup window to define classes and descriptions of assets. You can use classes to group assets according to account information, insurance information, depreciation rules, and other characteristics of each class for each book.


You must define at least one class because you're required to select a class when you add an asset to your records. When you add an asset record, accounts listed in the account group you specify in this window—if you use account groups—will be the default entries displayed in the Asset Account window. However, you can change the asset account group before saving the information in the Asset General Information window. If account numbers do not exist in the account group, default account entries from the Fixed Assets Company Setup window will be displayed. See [Account groups](#) on page 27 and [Creating an account group](#) on page 28, for more information.

You can change individual accounts for an asset using the Asset Account window or the account group ID. If you change the account group ID, the new accounts will be copied to the asset account record from the Account Group Setup window for the account group ID specified. See [Changing information for a group of assets](#) on page 81 and [Transferring multiple assets](#) on page 87 for information about changing account numbers assigned to groups of assets.

Although it's not required, you can enter a default insurance class ID that will be assigned to assets added using this class ID. When you add an asset and assign this class, the insurance class ID will be the default entry in the Asset Insurance window. However, you can change the insurance class ID for any of the individual asset account records. For more information, see [Setting up an insurance class record](#) on page 30.

To create a class record:

1. Open the Class Setup window.
(Microsoft Dynamics GP menu >> Tools >> Setup >> Fixed Assets >> Class)



2. Enter a class ID and description. The description will appear on reports and inquiries, and in maintenance windows.
3. You can enter an account group ID that will be the default account group for assets added with this class ID.

4. You can enter an insurance class ID that will define the inflation and depreciation rates for this class.
5. Choose Save.

Depreciation methods and calculations

Fixed Asset Management supports several depreciation methods. You can use this information to determine how the assets in your book class records should be depreciated. For more information, see [Creating a book class record](#) on page 21.

The special depreciation allowance is a percentage of depreciation in addition to the regular first-year depreciation amount. The special depreciation allowance is calculated before the first-year depreciation is calculated. Refer to current IRS regulations or consult a tax professional for information about what property is eligible for the special depreciation allowance, and what percentage applies.

If the property is also a passenger automobile, truck, van, or electric vehicle, there are yearly limits on the amount of depreciation you can claim. These limits vary, depending on the year the vehicle was placed in service, and whether or not you claim the special depreciation allowance.

The following table lists the depreciation methods and their calculations:

Depreciation method	Calculation
Straight-line Orig Life	$(\text{Cost} - \text{Salvage Value} - \text{Special Depreciation Allowance}) \div \text{Original Life in Years}$ If the Original Life includes days, the days will be converted to a fraction with days as the numerator and 365 as the denominator. For example, if the number of days is 146, the fraction would be displayed as 146/365.
Straight-line Rem Life	$(\text{Cost} - \text{Salvage Value} - (\text{LTD Depreciation Amount} - \text{YTD Depreciation Amount})) \div \text{Remaining Life in Days}$ This calculation determines the daily depreciation rate, which must be multiplied by the number of days in the year. This method is used when you select the Switch to Straight-Line option.
125% Declining Balance	$(\text{Cost} - (\text{LTD Depreciation Amount} - \text{YTD Depreciation Amount})) \div \text{Original Life} * 1.25$
150% Declining Balance	$(\text{Cost} - (\text{LTD Depreciation Amount} - \text{YTD Depreciation Amount})) \div \text{Original Life} * 1.50$
175% Declining Balance	$(\text{Cost} - (\text{LTD Depreciation Amount} - \text{YTD Depreciation Amount})) \div \text{Original Life} * 1.75$
200% Declining Balance	$(\text{Cost} - (\text{LTD Depreciation Amount} - \text{YTD Depreciation Amount})) \div \text{Original Life} * 2.00$
Sum of the Year's Digits	$(\text{Cost} - \text{Salvage Value} - \text{Special Depreciation Allowance}) * (\text{Remaining Life in Years} \div \text{Sum of Original Life in Years})$
Remaining Life	$(\text{Cost} - \text{Salvage Value} - (\text{LTD Depreciation Amount} - \text{YTD Depreciation Amount})) * (\text{Remaining Life in Years} \div \text{Sum of the Remaining Life in Years})$
Amortization	If you choose the Amortization depreciation method, you also must enter an amortization code and amortization amount or percent. Refer to Amortization codes on page 19 for more information.
ACRS Personal Property	Cost * Percentage from a table
ACRS Real Property	Cost * Percentage from a table
ACRS Real Property (Modified Straight Line)	Cost * Percentage from a table
ACRS Low Income Housing	Cost * Percentage from a table
ACRS Foreign Real Property	Cost * Percentage from a table
No Depreciation	No depreciation will be calculated for assets with this depreciation method. This method might be used for assets such as land.
Declining Balance	Net Book Value * Percentage

Amortization codes

If you're using the Amortization depreciation method, you must select the amortization codes and calculations. Refer to the table for more information.

Code	Calculation
Daily	Amortization Amount * 365 (or 366 if leap year)
Weekly	Amortization Amount * 52
Monthly	Amortization Amount * 12
Quarterly	Amortization Amount * 4
Yearly	Yearly Depreciation Amount = Amortization Amount
Percentage	(Cost Basis - (LTD Depreciation - YTD Depreciation)) * Percentage
Rate	(Cost Basis - Salvage Value - Special Depreciation Allowance) * Rate

The Initial Allowance Percentage field in the Asset Book window can be used in conjunction with the Amortization method of depreciation. If you enter a percentage, the percentage of the cost of the asset will be included in the first year depreciation amount, in addition to the normal first year depreciation amount.

Averaging conventions

Averaging conventions are guidelines for calculating depreciation in the year of the acquisition of the asset and the year of the disposal of the asset.

During the first year in service, depreciation is calculated using the depreciation method and averaging convention for the asset. The resulting depreciation amount is distributed over the period of time from the date it was placed in service to the last day of the year.



You should use the Mid-month (1st of month), Mid-month (15th of Month), Next Month, or Full Month averaging convention only if your fiscal periods are set up to match the calendar year.

The averaging convention does not change the dates an asset is retired or placed in service. The following averaging conventions are available in Fixed Asset Management.

Half-year Assets begin depreciating on the Place in Service Date. In the year of disposal, assets are retired on the last day of the first half of the year.

Only half of the depreciation amount is taken in the year an asset is acquired. This also applies to the year in which you dispose of an asset and to the year in which the life is complete, based on the original life of the asset. The asset doesn't depreciate after the first half of its final year.

Modified Half-Year Assets that are placed in service in the first half of the year will begin depreciating on the first day of the year.

Assets that are placed in service in the second half of the year will begin depreciating on the first day of the next year.

Assets with a retirement date in the first half of the year will be retired on the last day of the previous year.

Assets with a retirement date in the second half of the year will be retired on the last day of the year.

Mid-month (1st of month) Assets that are placed in service in the first half of the month—days 1 through 15—will begin depreciating on the first day of the month.

Assets that are placed in service in the second half of the month—day 16 through end of month—will begin depreciating on the first day of the next month.

Assets with a retirement date in the first half of the month—day 1 through 15—are considered retired on the last day of the previous month.

Assets with a retirement date in the second half of the month—day 16 through end of month—will be retired on the last day of the month.

Mid-month (15th of Month) Assets that are placed in service at any time during the month will begin depreciating on the 16th of the month. Assets that were placed in service in February will begin depreciating on the 15th of the month.

Assets retired at any time during the month will be retired on the 15th of the month of the retirement date. Assets retired in February will be retired on the 14th of the month.

Mid-quarter Assets that are placed in service at any time during the quarter will begin depreciating on the middle day of the second month of the quarter.

Assets retired at any time during the quarter are considered retired on the middle day of the second month of the quarter.

Next Month Assets that are placed in service at any time during the month will begin depreciating on the first day of the next month.

Assets retired any time during a month will be retired on the last day of the month.

Full Month Assets that are placed in service at any time during the month will begin depreciating on the first day of the month.

Assets retired at any time during the month are considered retired on the last day of the previous month.

Next Year Assets that are placed in service at any time during the year will begin depreciating on the first day of the next year.

Assets retired at any time during the year will be retired on the last day of the year.

Full Year Assets that are placed in service in the first half of the year will begin depreciating on the first day of the year.

Assets that were placed in service in the second half of the year will begin depreciating on the first day of the last half of the year.

Assets with a retirement date during the first half of the year will begin depreciating on the first day of the last half of the year. Assets with a retirement date during the second half of the year are considered retired on the last day of the first half of the year.

Full Year All Year Assets will begin depreciating on the first day of the year.

Assets with a retirement date anytime during the year will be retired on the last day of the previous year.

None Assets will begin depreciating on the date it was placed in service and will be retired on the retirement date.

Next Period Assets that are placed in service at any time during the period will begin depreciating on the first day of the next period.

Assets retired at any time during the period will be retired on the last day of the period.

Full Period Assets that are placed in service at any time during the period will begin depreciating on the first day of the period.

Assets retired at any time during the period will be retired on the last day of the preceding period.

Creating a book class record


Use the Book Class Setup window to enter specific depreciation information for each class and book combination. For example, suppose your business uses three types of books to track information for its assets—corporate books, federal tax books, and alternative minimum tax books. You must create three records in the Book Class Setup window for each asset class.

You can select a switchover method—straight-line or no switch—for depreciation assets. If you choose the straight-line method, the depreciation method for the asset will change to the straight-line remaining life depreciation method, when the depreciation for an asset is greater using the straight-line method than the current depreciation method the asset is using. Switchover for the asset will occur only at the beginning of the year when the yearly depreciation rate is calculated for the next year.

For more information about depreciation methods and averaging conventions, see [Depreciation methods and calculations](#) on page 17 and [Averaging conventions](#) on page 19.

To create a book class record:

1. Open the Book Class Setup window.
(Microsoft Dynamics GP menu >> Tools >> Setup >> Fixed Assets >> Book Class)



2. Select a book ID and a class ID.
3. Select a depreciation method and an averaging convention.
4. Select a switchover method.
5. Enter the Original Life to be used for assets assigned to this book class.
6. Mark Special Depr Allowance and enter the percentage of the cost basis of the asset book to be used for the special depreciation amount.
7. Mark the Salvage Estimate option if the salvage value of an asset assigned to this book class should be calculated.

If you marked Salvage Estimate, enter a salvage percentage. The percentage will be multiplied by the cost basis of each asset to calculate the salvage value.

8. Select Yes to apply US luxury auto limits to assets in this book class. These limits apply to tax books only.
9. You can mark the Luxury Van or Truck option or the Luxury Electric Auto option to apply luxury tax limits to assets in this book class, depending on the type of vehicle.
10. You can select the US Tax Equity Fiscal Responsibility Act (TEFRA) option used in calculating investment tax credit on assets placed in service prior to 1986. However, the TEFRA option isn't used for calculations in Fixed Asset Management.
11. Choose Save.

Chapter 2: Company setup options

You can use the Fixed Assets Company Setup window to define up to 15 user-defined fields and to enter Fixed Asset Management information for your company. For more information, refer to [Setting up user-defined field values](#) on page 35. You also can enter additional information to use if your system is integrated with Purchase Order Processing or Payables Management.

- [Asset account option](#)
- [Asset book options](#)
- [User data options](#)
- [Purchasing integration options](#)
- [Fixed assets purchasing transactions](#)
- [Setting up company records](#)

Asset account option

If Fixed Asset Management is integrated with General Ledger, you must mark Require Account in the Fixed Asset Company Setup window, and you must enter and save asset accounts before you can create a book record for an asset. If you mark Require Account, you must enter default account numbers for the company in the Default Accounts window. These accounts will be displayed for any asset account record with blank account numbers. For more information, refer to [Creating an account group](#) on page 28

Marking the Require Account option in the Fixed Asset Company Setup window requires that an asset account record includes all eight accounts before adding an asset book record. The asset account record will be added when the information from the Asset General Information window is added.

If future fixed assets transactions will be transferred to General Ledger, mark the Require Account option in the Fixed Assets Company Setup window.

Asset book options

You can mark the Auto Add Book Info option, to indicate that an asset book record should be created automatically when adding information in the Asset General Information window.

The Auto Add Book Info option also is included in the Asset General information window so you can choose not to include book information when adding an asset in cases where it's not appropriate to do so. If the Auto Add Book Info box is marked in the Book Setup window, and the asset book record for that book does not already exist, the asset book record for that book will be added automatically when the asset general information record is saved.

User data options

Mark the User Data Auto format option in the Fixed Asset Management Company Setup window to include user-defined fields in Fixed Asset Management windows. Choose the expansion button to open the Expand User Fields window to specify the name and format of user-defined fields. For more information, refer to [Setting up user-defined field values](#) on page 35.

If the User Data Auto Format option in the Company Setup window is marked, fields without spaces in the User Field Prompt fields will be displayed in the Asset User Data window and Fixed Assets Mass Change User window.

For example, if only five user-defined fields are to be used, when setting up the user fields on the Fixed Assets Company Setup window, enter spaces in the user field prompt of the fields that are not to be used. When the Asset User Data window is displayed, only the five fields that contain a user field prompt will be displayed.

Purchasing integration options

If you're using Purchase Order Processing or Payables Management, you can update Fixed Asset Management information by creating entries in those modules. The following options are available in the Fixed Assets Company Setup window.

Post PM through to FA Mark this option if you're using Payables Management. Fixed Asset Management will be updated if the account number entered on a PURCH type distribution line in Payables Management matches one of the account numbers in the Fixed Assets Purchasing Posting Accounts Setup window.

Post POP through to FA Mark this option if you're using Purchase Order Processing.

- If you mark the by Account option, Fixed Asset Management will be updated when the account number entered on a PURCH type distribution line in a Purchase Order Processing transaction matches one of the account numbers in the Fixed Assets Purchasing Posting Accounts Setup window.
- If you mark the by Receipt Line option, each purchase order line item for each purchase order receipt line that has the Capital Item option marked in the Purchasing Item Detail Entry window will be updated in Fixed Asset Management. You also can enter additional asset information that will be updated in Fixed Asset Management for each line item.

Include Matching Invoice Mark this option if you're using the Post POP through to FA option and if a separate record should be created for each receipt line matched with an invoice amount that is different from the receipt amount.

Fixed assets purchasing transactions

If Fixed Asset Management is integrated with Payables Management or Purchase Order Processing, information from those modules is transferred to the Fixed Assets Purchasing Transactions window. The information will be stored in the Fixed Asset Management purchasing transactions table until you complete one of the following steps:

- Delete a transaction in the Fixed Assets Purchasing Transactions window. Refer to [Deleting fixed assets purchasing transactions](#) on page 119 for more information.
- Mark the Delete Purchasing Transactions Immediately option in the Fixed Assets Company Setup window. When the total amount of the purchase has been applied to one or more assets, and the unapplied amount is zero, the record will be deleted automatically.


- Delete all transactions that have been fully applied to assets where the unapplied amount is zero. For more information, refer to [Deleting fixed assets purchasing transactions](#) on page 119.

Setting up company records


Use the Fixed Assets Company Setup window to create user-defined fields, enter information if your system integrates with Payables Management or Purchase Order Processing, and select default guidelines for your system. Refer to [Using Fixed Asset Management with Payables Management](#) on page 51 and [Using Fixed Asset Management with Purchase Order Processing](#) on page 54 for more information.

To set up company records:

1. Open the Fixed Assets Company Setup window.
(Microsoft Dynamics GP menu >> Tools >> Setup >> Fixed Assets >> Company)



2. Select the book that will be used for corporate depreciation and that General Ledger transactions come from.
3. Mark the Require Account option to require that an Asset Account record includes all eight accounts before adding an Asset Book record. For more information, refer to [Asset account option](#) on page 23.
4. Choose the Default Accounts expansion button to open the Default Accounts window.



5. Select an Account Group to copy the accounts assigned to the group into the Company Setup record. You also can enter each account individually or change specific accounts after you select an Account Group. For a description of each account type, refer to [Creating an account group](#) on page 28. Choose OK.
6. In the Fixed Assets Company Setup window, mark Auto Add Book Info. For more information, refer to [Asset book options](#) on page 23.
7. Mark User Data Auto Format to leave a user field blank. The user field won't be displayed in the User Data window.
8. Choose the User Fields expansion button to open the Expand User Fields window where you can define up to 15 user-defined fields. You also can define default values for the user-defined fields in the User Fields List Setup. Refer to [User data options](#) on page 23 for more information.

For more information about entering default values for these fields, refer to [Setting up user-defined field values](#) on page 35.

9. Choose OK to close the Expand User Fields window.
10. In the Fixed Asset Company Setup window, mark the Purchasing Integration Options. Refer to [Purchasing integration options](#) on page 24 for more information.
11. Mark the Default Asset Label from Asset ID option to copy the asset ID and suffix to the Asset Label field automatically when you add an asset.
12. Mark Validate Custodian if the custodian records you enter in the Asset General Information window should be verified as a valid employee records.
13. Mark Allow Reporting Ledgers to enable BASE, LOCAL and International Financial Reporting Standards (IFRS) ledgers for Fixed Assets. When this option is marked, you can assign books already created, as well as new Fixed Assets books to update one of these reporting ledgers.

This option is available only if you have marked the Allow check box for the Reporting Ledgers option in the General Ledger Setup window (Microsoft Dynamics GP menu >> Tools >> Setup >> Financial >> General Ledger). Refer to the General Ledger documentation for more information.

14. Choose Save.

Chapter 3: Optional setup procedures

Depending on how your business is structured, you might want to set up additional records, such as account groups, posting accounts, insurance classes, lease company records, and location records.

The following information is discussed:

- [Account groups](#)
- [Creating an account group](#)
- [Entering fixed assets posting accounts](#)
- [Setting up an insurance class record](#)
- [Creating a lease company record](#)
- [Creating a location record](#)
- [Creating a physical location record](#)
- [Creating a retirement code](#)
- [Creating a structure ID](#)
- [Setting up user preferences](#)
- [Setting up user-defined field values](#)

Account groups

Although you're not required to set up account groups, using them can speed up the process of entering account records when you add assets to your system. For instance, you can define an account group for each class of assets that you set up using the Class Setup window, and then apply the default account group to assets you add to the class. When you add or change an individual asset, you will use the Account Group ID field in the Asset General Information window to add or change account group information for the asset. You also can use the Account Group ID field in the Asset Account window when changing an individual asset.

If you're not using asset accounts, unmark the Require Account option in the Fixed Assets Company Setup window so that you're not required to enter account information.

If you don't use account groups in your system, you can set up default accounts in the Fixed Assets Company Setup window and then apply an account record to each asset you add to your system. After viewing default accounts in the Asset Account window, you can change the account information, if necessary.

Refer to [Chapter 17, "Financial detail file activity,"](#) for more account information.

You can select up to eight of the following accounts for each account group:

Depreciation Expense Used to record current year depreciation expense.

Depreciation Reserve Used to record depreciation reserve or accumulated depreciation.

Prior Year Depreciation Used to record any depreciation expense that relates to years prior to the current fiscal year. This account number might be the same account specified as the depreciation expense account.

Asset Cost Used to record the cost of an asset. It is debited when you add an asset and is credited when you retire an asset. It also is debited or credited when you change the cost of the asset.

Proceeds Used to record the sum of Cash Proceeds and Non-Cash Proceeds when an asset is retired or disposed of.

Usually, the cash receipt for the disposal is recorded somewhere else in the accounting process, like Bank Reconciliation cash receipts or Receivables Management cash receipts, if you're using these modules. These processes would typically post a debit amount to the actual general ledger cash account. The offsetting credit entry amount would be posted to the account entered in the proceeds account. When the retirement transaction is posted from Fixed Asset Management, the proceeds account will be debited.

Recognized G/L Used to record recognized gain or loss that is calculated when you dispose of or retire an asset.

Non Recognized G/L Used to record the non-recognized gain or loss that is calculated when you dispose of or retire an asset.

Clearing If this account is used as a "true" clearing account, it is debited in General Ledger for the PURCH type distribution line in the Purchasing Distribution Entry window when you post in Payables Management or Purchase Order Processing. This account is credited in General Ledger when an asset is added and credited or debited when the asset cost is changed to offset the cost entry. If the balance in the clearing account is zero at the end of each period, items in Purchasing Order Processing or Payables Management that need to be capitalized were added as fixed asset records.

If Fixed Asset Management should not affect General Ledger when assets are added to your system, enter the same account in the clearing account that you enter in the asset cost account.

Creating an account group

Use the Account Group Setup window to define groups of Fixed Asset Management accounts. For more information about using account groups in your company refer to [Account groups](#) on page 27.

To create an account group:

1. Open the Account Group Setup window.
(Microsoft Dynamics GP menu >> Tools >> Setup >> Fixed Assets >> Account Group)

2. Enter an account group ID and description to identify a group of accounts.
3. Enter or select account numbers for each of the accounts in the account groups. For a description of each account, refer to [Account groups](#) on page 27.
4. Choose Save.

Entering fixed assets posting accounts

If you're also using Payables Management or Purchase Order Processing—and have marked the by Account option in the Fixed Assets Company Setup window—you must set up accounts that will determine how and if fixed assets capital acquisition transactions will be posted to Fixed Asset Management when you enter vouchers in Payables Management or receipts in Purchase Order Processing.

Fixed Asset Management will be updated if the account you specify in a purchasing transaction also exists in the Fixed Assets Purchasing Posting Accounts Setup window.

Before you enter posting accounts, you must mark the following options in the Fixed Assets Company Setup window:

- Post PM through to FA
- Post POP through to FA
- by Account




These accounts are not used by Purchase Order Processing if you mark the by Receipt Line option in the Fixed Assets Company Setup window.

Refer to [Purchasing integration options](#) on page 24 for more information.

Use the Fixed Assets Purchasing Posting Accounts Setup window to enter account numbers that determine if a fixed asset recorded in Payables Management or Purchase Order Processing also will be posted to Fixed Asset Management.

To enter fixed assets posting accounts:

1. Open the Fixed Assets Purchasing Posting Accounts Setup window. (Microsoft Dynamics GP menu >> Tools >> Setup >> Fixed Assets >> Purchasing Posting Accounts)



2. Choose Assigned to view only accounts already entered in this window. Choose All to view all the accounts in your chart of accounts.
3. Enter or select an account number for a clearing account that will be used in Payables Management or Purchase Order Processing for a record you're adding to the Fixed Assets purchasing transactions file. For more information about clearing accounts, refer to [Account groups](#) on page 27.
4. You can enter or select a default class ID. If you're using Payables Management or Purchase Order Processing and have marked the by Account option in the Fixed Assets Company Setup window and the account number for this posting account setup record is entered as the Purchase account, this will be the default class ID for this account in the Asset General Information window.
5. Choose Save.

Setting up an insurance class record


You can set up insurance classes to group and record assets according to similar insurance inflation and depreciation rates.

After you've set up an insurance class, you can assign the insurance class to asset classes in the Class Setup window. When you add an asset record to your system, the insurance class that you enter in the Class Setup window will be the default entry for the asset in the Asset Insurance window.

Use the Insurance Setup window to enter insurance class ID records.

To set up an insurance class record:

1. Open the Insurance Setup window. (Microsoft Dynamics GP menu >> Tools >> Setup >> Fixed Assets >> Insurance)



2. Enter an insurance class ID and description.

3. Enter an inflation rate. This rate is expressed in net inflated value based on original reproduction cost. You would enter a 10% inflation rate as 110.00.
4. Enter a depreciation rate. This rate is expressed as an accumulative percentage of original reproduction cost.
5. Choose Save.


Creating a lease company record

Use the Lease Company Setup window to specify which companies you can lease assets from. Lease companies that you create here will be displayed in the Asset Lease window.

Although it's not required, you also can assign a vendor ID to the lease company. Vendor IDs displayed in this window were set up in the Vendor Maintenance window in Payables Management.

To create a lease company record:

1. Open the Lease Company Setup window.
(Microsoft Dynamics GP menu >> Tools >> Setup >> Fixed Assets >> Lease Company)



2. Enter the name of the lease company.
3. If your system is integrated with Payables Management, you also can enter or select a vendor ID.
4. Choose Save.


Creating a location record

Use the Location Setup window to define valid locations for your company. Entries you make for city, county, and state codes are optional, but the information might be useful to include on property tax or other report.

Use the Asset General Information window to assign a location ID to an asset record.

To create a location record:

1. Open the Location Setup window.
(Microsoft Dynamics GP menu >> Tools >> Setup >> Fixed Assets >> Location)



2. Enter the location ID—for property tax purposes—to be associated with the location you’re defining.
3. Enter city, state, and county codes, as well as their corresponding descriptions.
4. Choose Save.


Creating a physical location record

Use the Physical Location Setup window to define physical locations. Physical location information isn’t required to set up asset records in the Asset General Information window. However, use this window to set up physical location IDs.

Any location IDs you enter in this window first must be set up using the Location Setup window. For more information, refer to [Creating a location record](#) on page 31.

To create a physical location record:

1. Open the Physical Location Setup window.
(Microsoft Dynamics GP menu >> Tools >> Setup >> Fixed Assets >> Physical Location)




2. Enter a physical location ID, and a description.
3. Enter or select the location code for the physical location ID. Location codes entered in this window will appear as default entries in the Asset General Information window when you enter the corresponding physical location ID.
4. You can enter a last inventory date. It will be updated when you reconcile your inventory using the Physical Inventory window.
5. Choose Save.

Creating a retirement code

Use the Retirement Setup window to define retirement codes that you can enter when disposing of assets. You must define retirement codes before you can enter retirement information for an asset. Retirement codes also can be useful for reports.

To create a retirement code:

1. Open the Retirement Setup window.
(Microsoft Dynamics GP menu >> Tools >> Setup >> Fixed Assets >> Retirement)



2. Enter a code to describe a retirement.
3. Choose Save.


Creating a structure ID

You can define structure IDs to provide additional information about assets when you set them up using the Asset General Information window. For example, you could assign assets to cost centers.

Use the Structure Setup window to define structure IDs that can be entered when adding asset general information.

To create a structure ID:

1. Open the Structure Setup window.
(Microsoft Dynamics GP menu >> Tools >> Setup >> Fixed Assets >> Structure)



2. Enter a structure ID and a corresponding description.
3. Choose Save.

Setting up user preferences


You can use the Fixed Assets User Preferences window to display the path settings to specific import and export files used by Fixed Asset Management. This information is in the Dex.ini file for each workstation, but you can change it in this window.

If a field is left blank in the Fixed Assets User Preference window, the default value from the installation process will be displayed in the field. As each process is run, the last value used will be displayed in the field. Default import and export file names and descriptions are listed in the following table:

File	Filename	Description
Physical Inventory Import file	PhysInv.txt	Allows asset label and physical inventory location information to be collected using a bar-code reader or other external sources, and imported into Fixed Asset Management.
Asset Group Import file	AssetGrp.txt	Used to create an asset group using a list of fixed assets from an external source. The asset group can be used in any Fixed Asset Management function that can access a group, such as mass transfer, mass retirement, mass change, projection and depreciation.
Physical Inventory Information Import file	PhysInfo.txt	Adds asset label, physical location IDs, or both to existing assets.
Asset Import file	Asset.txt	Allows importing assets from an external source.
Macro file	Assets.mac	Processing the addition of asset from an external source. The macro is created from the Asset Import file.
Asset ID Export file	AssetID.txt	Asset IDs are exported from Fixed Asset Management to the Asset ID Export file.
Asset Label Export file	AssetLBL.txt	Asset labels are exported from Fixed Asset Management to the Asset Label Export file.
Sample Data		The sample data files to use with Fabrikam, Inc. sample company. They are installed during the Microsoft Dynamics GP installation.

To set up user preferences:

1. Open the Fixed Assets User Preferences window.
(Microsoft Dynamics GP menu >> Tools >> Setup >> Fixed Assets >> User Preferences)




2. Verify or change the paths.
3. Choose Save.

Setting up user-defined field values


You can create default values for user-defined fields one through ten in the Expand User Fields window. You can then select these values in the Asset User Data window. If the values are dates, you can verify the information.

To set up user-defined field values:

1. Open the Expand User Fields window.
(Microsoft Dynamics GP menu >> Tools >> Setup >> Fixed Assets >> Company >> User Fields expansion button)



2. Enter user-defined field names and select a format for the fields to use.
3. Mark the List Valid Values option for each user field to add values to be used in that field.
4. Choose the expansion button to open the User Fields List Setup window and enter data to be used as default field information.



5. If the format is a date format, you can mark the Valid Date option to require a valid date entry in the Asset User Data window.
6. Choose OK to close the window.
7. Choose Save in the Fixed Assets Company Setup window to save your changes.

Part 2: Cards and integration

This part of the documentation provides information about asset records. It also explains how to import information from other sources and how Fixed Asset Management integrates with other Microsoft Dynamics GP modules.

This part includes the following information:

- [Chapter 4, “Fixed Asset Management cards,”](#) explains how to create asset records, including insurance and user-defined information.
- [Chapter 5, “Additional Fixed Asset Management cards,”](#) explains how to create additional records for each asset, including investment tax credit information and lease information.
- [Chapter 6, “Integration,”](#) describes how to transfer information between Payables Management and Fixed Asset Management and between Purchase Order Processing and Fixed Asset Management. It also explains how to use Fixed Asset Management with Multicurrency Management.
- [Chapter 7, “Asset import,”](#) explains the information needed to import asset data from another fixed assets system or a different source into Fixed Assets Management.

Chapter 4: Fixed Asset Management cards

You can create records for each asset that include account, depreciation, insurance, user data, and general information. You must create an asset general information record before adding any other records for the asset.

Some of the default options and information that you entered when setting up Fixed Asset Management will be displayed when you create asset records. You can accept these entries or enter other information.

The following information is discussed:

- [*Creating an asset record*](#)
- [*Adding asset records from other modules*](#)
- [*Modifying an asset account record*](#)
- [*Class IDs and account groups*](#)
- [*Creating an asset book record*](#)

Creating an asset record

Use the Asset General Information window to enter an asset general information record for each asset in Fixed Asset Management.

If you're using Payables Management or Purchase Order Processing, you can enter information in Purchase Order Processing or Payables Management, and then update the information in Fixed Asset Management. Refer to [*Using Fixed Asset Management with Payables Management*](#) on page 51 and [*Using Fixed Asset Management with Purchase Order Processing*](#) on page 54 for more information.

When you enter an asset ID, you also must enter a suffix for it. The asset ID is used throughout Fixed Asset Management to identify assets; the suffix is used to identify components of assets. The default suffix is 1. You can accept the default suffix or enter or select a different one.

Only a few of the fields in the Asset General Information window are required: Asset ID, Description, Class ID, Type, Property Type, Acquisition Date, and Quantity. You have the option to enter information in the other fields in the window.

To create an asset record:

1. Open the Asset General Information window.
(Cards >> Fixed Assets >> General)


2. Enter an asset ID, asset suffix, and a description of the asset.
3. You can enter an extended description and a short name for the asset, which can be displayed on reports and inquiries.
4. You can enter or select a master asset ID. A master asset ID is used to group components of a single asset or related assets. For example, a computer could be an asset that contains a CPU, a monitor, and a printer as components. You can assign the same master asset ID to each component so that the components are related and can be tracked together, even if they become separated over time. You also can change the master ID of an asset.
5. Enter or select a class ID and select an asset type and property type, or you can accept the default types.
6. You can enter or select an account group ID to assign account numbers to the asset.
7. Enter an acquisition date. The acquisition date will be the default date the asset was placed in service and will be the depreciated-to date in the Asset Book Information window.
8. You can enter or select a different currency ID.



If you use Multicurrency Management and you select a currency ID that's different from the functional currency defined for this company, the functional currency will be calculated based on the appropriate exchange rate. The functional currency will be used to calculate the original acquisition cost displayed in the Asset Purchase window, based on the exchange rate.

9. If the Currency ID displayed is the functional currency, you can enter the acquisition cost or choose the Acquisition Cost expansion button to open the Asset Purchase window and enter detailed information about the acquisition cost.

You can enter the acquisition cost in the Asset Purchase window or the Asset General Information window. If you enter the acquisition cost in the Asset General Information window, information will be transferred to the Asset Purchase window. You can change the information in the Asset Purchase window.



The acquisition cost displayed in the Asset General Information window is the sum of all the acquisition costs in the Asset Purchase window.

- If the Currency ID displayed is not the functional currency, you can enter a value in the Orig. Acquisition Cost field.

You can enter the currency ID in the Asset Purchase window or the Asset General Information window. If you enter the currency ID in the Asset General Information window, information will be transferred to the Asset Purchase window. You can change the information in the Asset Purchase window.

- You can enter or select a physical location ID and enter an asset label.
- You can enter or select a structure ID and custodian ID. The structure ID further describes the structure this asset is a part of; for example, to identify a cost center.
- You can enter a manufacturer name and enter or select a location ID. The location ID indicates where the item is located for property tax purposes.
 - Choose the Manufacturer Name expansion button to enter the serial number, model number, and warranty information.
 - Choose the Location ID expansion button to enter an assessed value for the item.
- Enter the quantity of this asset. The default quantity is 1. The first time you create an asset general information record, this quantity is the beginning quantity amount.
- You can enter the date maintenance was last done on this asset and the date the asset was added. The default date is the system date when this record was created.
- Choose Save.

Adding asset records from other modules

If you are using Payables Management or Purchase Order Processing, you can create asset records from information entered in these modules.

Refer to [Chapter 6, “Integration,”](#) for more information about integrating Fixed Asset Management with other Microsoft Dynamics GP modules.


Modifying an asset account record

Use the Asset Account window to modify an asset account record. You can change the account numbers to be used when posting information for each asset. You can't create a new account in this window, only assign existing accounts to the asset.

No accounting entry is automatically made if you change an account here. If you change the account by using the Fixed Assets Mass Transfer window instead, you can enter a transfer date and entries are made based on that date. For more information, see [Transferring multiple assets](#) on page 87.

To modify an asset account record:

1. Open the Asset Account window.
(Cards >> Fixed Assets >> Account)



2. Enter or select an asset ID and suffix.
3. You can enter or select an account group ID.
4. Enter or select different account numbers for any of the accounts.
5. Choose Save.

Class IDs and account groups

When you create a general information record for an asset, you must assign the asset to a class ID. To assign an account group with up to eight account numbers to each class ID, refer to [Creating a class record](#) on page 16.

You can change the account group before saving the asset general information record. Accounts in the account group will be saved in the asset account record when you add asset general information. If you don't enter accounts in the account group the company default accounts selected in the Fixed Assets Company Setup window will be displayed.

The account group ID in the asset account record is displayed only before the asset account record is saved. After you save the asset account record, you can enter a new account group. These new accounts will be used for all future processing for the asset.

Creating an asset book record

Use the Asset Book window to add asset book records and enter depreciation-related information. Default entries for information, such as the date an asset was placed in service, depreciation date, original life, and depreciation method, averaging convention, and switchover method, will be displayed; however, you can change any of the information in the Asset Book window.

You can choose the Distribution button to view and modify the distribution information that will be saved in the Financial Detail table for transactions entered in this window.


You must have completed the following steps before entering information in this window.

- Created an asset general information record. (Refer to [Creating an asset record](#) on page 39 for more information.)
- Created an asset account record, if Require Account was marked in the Fixed Assets Company Setup window. (Refer to [Asset account option](#) on page 23 for more information.)
- Created a book setup record for the book being added. (Refer to [Creating a book record](#) on page 14 for more information.)

A book class record must exist for the book being created for the class assigned in the Asset General Information window for this asset. For example, if the corporate book for this asset is being created and the class ID in the Asset General Information window for this asset is 101, there must be a book class record for class 101, book ID corporate. Refer to [Creating a book class record](#) on page 21 for more information.

To create an asset book record:

1. Open the Asset Book window.
(Cards >> Fixed Assets >> Book)



2. Enter or select an asset ID and suffix.
3. Select a book ID to add for this asset.
4. Enter the date the asset was placed in service and a depreciation date, or accept the default dates. The default dates will be the acquisition date for the asset from the Asset General Information window.

Don't change the default depreciation date if you're not entering depreciation balances for year-to-date or life-to-date depreciation. You can enter a depreciation amount for the year only when adding a transaction if the depreciated-to date is in the current fiscal year.



If you are entering year-to-date and life-to-date depreciation balances, you might need to enter a depreciated-to date that is equal to or later than the place-in-service date. Calculations for depreciation begin on the day after the depreciated-to date.

5. You can enter the cost basis amount for the asset. The default cost basis entry for each field is the acquisition cost from the Asset General Information window. The cost basis in the corporate book is the amount added to the applied value if the information for this asset was entered in Payables Management or Purchase Order Processing.
6. You can enter salvage value, year-to-date depreciation, and life-to-date depreciation amounts for assets—even if prior depreciation balances exist. If you enter a year-to-date amount, the following entries also must be made:
 - Enter a depreciated-to-date the same as or later than the place-in-service date.
 - Enter a life-to-date depreciation amount the same as or greater than the year-to-date depreciation amount.
7. You can change the following default entries: depreciation method, averaging convention, switchover method, original life, amortization code, amortization amount/percentage, TEFRA, initial allowance percentage, special depreciation allowance, and luxury automobile.

Refer to [Depreciation methods and calculations](#) on page 17 and [Averaging conventions](#) on page 19 for more information.

8. If the asset is to be depreciated using US luxury automobile limits and you selected a tax book for this asset, select Yes for the Luxury Auto field; otherwise, select No.
9. You can mark the Luxury Van or Truck option or the Luxury Electric Auto option to apply luxury tax limits to assets in this book class, depending on the type of vehicle.
10. You can choose the Distribution button to open the Financial Detail Maintenance window and view the distribution information for this transaction.
11. Choose Save.

Chapter 5: Additional Fixed Asset Management cards

You can create additional records for each asset that can include U.S.s investment tax credit, insurance, lease, and user-defined information.

Some of the default options and information that you entered when setting up Fixed Asset Management will be displayed when you create asset records. You can accept these entries or enter other information.

The following information is discussed:

- [*Using Section 179 Expense Deduction*](#)
- [*Creating an asset book ITC record*](#)
- [*Adjusting the cost basis to equal the net cost basis*](#)
- [*Creating an asset insurance record*](#)
- [*Creating an asset lease record*](#)
- [*Creating an asset user-defined record*](#)

Using Section 179 Expense Deduction

US Tax Section 179 Expense Deduction allows expensing all or a portion of the cost of an asset in the year of acquisition, rather than depreciating the cost over the life of the asset. Any portion of the asset cost taken as Section 179 cannot be taken also as depreciation. Any portion not expensed as Section 179 is depreciated over the life of the asset. The depreciable basis—reflected in the Net Cost Basis field in the Asset Book ITC window and in the Cost Basis field in the Asset Book window—is reduced by the Section 179 amount. Certain restrictions and rules apply, including:

- Valid for Personal Property only
- Yearly Section 179 maximums
- Year 2000 - \$20,000
- Year 2001–2002 - \$24,000
- Year 2003, 2004, 2005 - \$100,000
- \$400,000 ceiling – reduces allowable Section 179 amount dollar for dollar for the amount of total acquisitions in the year over the ceiling
- Any portion of the allowable amount can be designated to any of the year's acquisitions, including all or a portion of a specific asset's cost

If the entire cost of an asset is recorded as a Section 179 expense, the depreciable cost basis of the asset is reduced to \$0 and the asset is marked fully depreciated. The Depreciated to Date field in the Asset Book window should be changed to the last day of the year.

The cost basis for the asset book reflects only the depreciable basis. Therefore, the Original Cost field in the Asset Book ITC window should be referenced when reporting on the acquisition cost of Section 179 assets. For example, to determine the total of all eligible Section 179 acquisitions for the year you need to consider the total acquisition costs for the year.

The total acquisition cost is the sum of original cost in the Asset Book ITC window, if it exists, and the cost basis in the Asset Book window, when an original cost is not available.

Creating an asset book ITC record

Use the Asset Book ITC window to add US tax S179 information, US investment tax credit (ITC) information, and make other adjustments to the cost basis of an asset. The default original cost basis and net cost basis values will be equal to the cost basis of the asset book record that you selected. When you save the record, the Net Cost Basis field is calculated as follows:

Original Cost Basis – Section 179 Exp. Ded. – ITC Cost Red. Amount + or -Misc. Cost Adjustment

You can add investment tax credit information in the TEFRA, ITC Taken, ITC Allowed, and ITC Recapture fields. This information isn't used for any calculations, although it might be useful to include on reports.

To create an asset book ITC record:

1. Open the Asset Book window.
(Cards >> Fixed Assets >> Book)
2. Enter or select an asset ID and suffix and select a book ID.
3. Choose ITC/Cost to open the Asset Book ITC window.

The screenshot shows the 'Asset Book ITC' window with the following data:

Asset ID:	00001	1	Desk
Book ID:	CORPORATE		Corporate
Original Cost Basis			\$1,100.00
Sec. 179 Exp. Ded.			\$100.00
ITC Cost Red. Amount			\$100.00
Misc. Cost Adjustment			\$100.00
Net Cost Basis			\$1,000.00
TEFRA:		None	
ITC Taken			\$100.00
ITC Allowed			\$100.00
ITC Recapture			\$100.00

Buttons: Save, Delete

4. You can change the original cost basis of the asset, if necessary.
5. Enter a Section 179 expense deduction. The Section 179 expense reduces amount in the calculation for net cost basis.
6. You can enter an ITC Cost Reduction amount. This amount reduces the amount in the calculation for net cost basis.
7. You can enter a Miscellaneous Cost Adjustment amount. This amount will be added to the original cost basis when calculating the net cost basis.
8. You can enter information in the fields that are related to investment tax credit. Enter the amount of investment tax credit that was taken, allowed, and recaptured for this asset.
9. Select a TEFRA option or accept the default option. This option isn't used for calculations in Fixed Asset Management.
10. Choose Save to save the asset book ITC record.

Adjusting the cost basis to equal the net cost basis

If the data in the Net Cost Basis field in the Asset Book ITC window does not equal the data in the Original Cost Basis field, the cost basis will be adjusted to match the net cost basis. When you save an asset book record, you also must select a depreciation recalculation option for that asset. You can choose from the following options:

Reset Life Recalculates depreciation from the date it was placed in service to the date the asset has already been depreciated to. If there are adjustments to the depreciation for any period, they will be saved and displayed in the Asset Book window.

Reset Year Recalculates depreciation from the beginning of the year to the date the asset has already been depreciated to. If there are adjustments to the depreciation for any period, they will be displayed in the Asset Book window.


Recalculate Calculates a new rate of depreciation using the new cost basis data, but does not make adjusting entries for depreciation already taken. The new rate of depreciation will be used the next time the depreciation routine is completed.

Creating an asset insurance record

Use the Asset Insurance window to record insurance information for an asset. You can enter a replacement cost, a reproduction cost—the amount it would take to replace the asset, not including depreciation considerations—and an exclusion amount and type.

To create an asset insurance record:

1. Open the Asset Insurance window.
(Cards >> Fixed Assets >> Insurance)



2. Enter or select an asset ID and suffix.
3. Enter or select an insurance class, or accept the default entry. You can use the insurance class to group assets that appreciate or depreciate at the same rate.
4. Enter the insurance year—the year the reproduction cost is based on.
5. Enter the amount it would take to replace the asset, not including depreciation considerations, in the Replacement Cost field.
6. Enter the amount it would cost to reproduce the same asset using current year's prices in the Reproduction Cost field.


7. Enter the reproduction cost less any amount attributable to depreciation in the Depr. Repro. Cost field.
8. Enter the exclusion amount for the asset. This is the cost of the asset that is not included for insurance purpose. For example, if this asset is a building, and the foundation is not covered for insurance purposes, you would enter the cost of the foundation.
9. Enter an exclusion type. You can use a code to describe why the amount in the exclusion amount field is not included for insurance purposes.
10. Choose Save.

Creating an asset lease record

Use the Asset Lease window to create a lease record for any assets that are leased by your company, such as a car or office furniture.

To create an asset lease record:

1. Open the Asset Lease window.
(Cards >> Fixed Assets >> Lease)



2. Enter or select an asset ID and suffix.
3. Enter or select a lease company ID and select a lease type.
4. Enter the contract ID associated with this leased asset.
5. Enter the payment, interest rate, and lease end date for this leased asset.
6. Choose Save.

Creating an asset user-defined record

Use the Asset User Data window to create up to 15 user-defined asset data fields to track additional information for an asset. For example, you could save asset characteristics for a computer, such as hard disk size, processor size, and the operating system.

For more information, refer to [Setting up user-defined field values](#) on page 35.

To create an asset user-defined record:

1. Open the Asset User Data window.
(Cards >> Fixed Assets >> User Data)

The screenshot shows the 'Asset User Data' window. At the top, there is a title bar with 'Asset User Data' and standard window controls. Below the title bar is a toolbar with 'Save', 'Clear', and 'Delete' buttons, and a 'Redisplay' checkbox. The main area contains a table with the following structure:

Asset ID	Status
	Active
User Field 1	
User Field 2	
User Field 3	
User Field 4	
User Field 5	
User Field 6	
User Field 7	
User Field 8	
User Field 9	
User Field 10	
User Field 11	\$0.00
User Field 12	\$0.00
User Field 13	\$0.00
User Field 14	\$0.00
User Field 15	\$0.00

At the bottom of the window, there is a navigation bar with navigation icons and a dropdown menu set to 'by Asset ID'.

2. Enter or select an asset ID and suffix.
3. Enter or select user field data. You can select field data only if you created default field values. Refer to [Setting up user-defined field values](#) on page 35 for more information.
4. Choose Save.

Chapter 6: Integration

You can add an item in Payables Management or buy an item in Purchase Order Processing and transfer that information to Fixed Asset Management. To transfer information, Fixed Asset Management must be installed on the same machine that Payables Management transactions or Purchase Order Processing receiving transactions are posted from.

You can assign more than one transaction, including both Payables Management and Purchase Order Processing transactions, to the same asset. You also can change transactions that have been assigned to an asset and assign the same transaction to multiple assets. If you assign a transaction to an existing asset, you must update the asset book information manually.

For information about the integration with General Ledger, refer to [Chapter 14, "General Ledger integration."](#)

The following information is discussed:

- [Using Fixed Asset Management with Payables Management](#)
- [Adding asset records from Payables Management](#)
- [Using Fixed Asset Management with Purchase Order Processing](#)
- [Integration options for Purchase Order Processing](#)
- [Adding asset records from Purchase Order Processing—by Account option](#)
- [Adding asset information after receiving purchasing transactions](#)
- [Adding asset records from Purchase Order Processing—by Receipt Line option](#)
- [Using Fixed Asset Management with Multicurrency Management](#)

Using Fixed Asset Management with Payables Management

To enter assets in Payables Management and track them in Fixed Asset Management, mark the Post PM through to FA option in the Fixed Assets Company Setup window. For more information, refer to [Purchasing integration options](#) on page 24.

If you're using Payables Management, you must add at least one special account in the Fixed Assets Purchasing Posting Accounts Setup window. When you create an invoice in Payables Management for an asset item, the account entered on the PURCH-type distribution line in the Payables Transaction Entry Distribution window must match an account in the Posting Accounts Setup window.

You can create one or more asset records from a Payables Management transaction, in the Fixed Assets Purchasing Transactions Display window until the total amount of the line item has been applied. The applied amount in the Fixed Assets Purchasing Transactions Display window will be updated when you choose Save in the Asset General Information window. You can view the information from the selected Payables Management transaction in the Asset Purchase window.

The following table displays the information that's transferred to Fixed Asset Management from Payables Management.

From Payables Management field	To Fixed Asset Management field
Vendor ID	Vendor ID
Voucher Number	Control Number
Document Date	Acquisition Date
Document Date	Document Date
Document Number	Document Number
Transaction Source (PMTRX Prefix)	Transaction Source
Voucher Description	Description (Asset Purchase window)*
Purchase Order Number	Purchase Order Number
PURCH-type distribution amounts	Acquisition Cost and Originating Acquisition Cost
*If there are multiple transactions, the primary transaction's voucher description will be displayed in the Asset Description field in the Asset General Information window.	

If the payables transaction uses Multicurrency Management, the following fields are transferred:

From Payables Management field	To Fixed Asset Management field
Currency ID	Currency ID
Currency Index	Currency Index
Exchange Rate	Exchange Rate
Exchange Date	Exchange Date
Time	Time
Exchange Table ID	Exchange Table ID
Rate Type ID	Rate Type ID
Rate Calc Method	Rate Calc Method
Denomination Exchange Rate	Denomination Exchange Rate
MC Trx State	MC Trx State

For more information about setting up the integration between Fixed Asset Management and Payables Management, refer to the following information: [Entering fixed assets posting accounts](#) on page 29 and [Deleting fixed assets purchasing transactions](#) on page 119.

Adding asset records from Payables Management

If Post PM through to FA is marked in the Fixed Assets Company Setup window, you can create a Fixed Asset Management record using information that's been entered in Payables Management. You can select one or more Payables Management transactions for each asset record.

Use the Asset General Information window to create an asset record. Use the Fixed Assets Purchasing Transactions window to transfer information from transactions created in Payables Management to asset records in Fixed Asset Management.


Only a few of the fields in the Asset General Information window are required. The required fields are:

- Asset ID
- Description
- Class ID
- Type
- Property Type
- Acquisition Date
- Quantity

You have the option to enter information in the other fields in the window.

To add asset records from Payables Management:

1. Open the Asset General Information window.
(Cards >> Fixed Assets >> General)
2. Enter an asset ID and suffix.
3. Choose Purchase to open the Fixed Assets Purchasing Transactions window.
The Purchase button is available only if there are transactions in the Fixed Assets Purchasing Transactions window.



4. Mark the M box for each transaction to assign that transaction to the asset. Mark the P box for the primary transaction. Information from the primary transaction will be displayed in the Asset General Information window and the Asset Purchase window. Information from other selected transactions will be displayed in the Asset Purchase window only.
5. Choose OK to save the information from the selected transactions to the Asset General Information window and the Asset Purchase window.
6. In the Asset General Information window, enter any additional information.

You can enter an acquisition cost, currency ID, and originating acquisition cost in the Asset General Information window only if you haven't selected any purchasing transactions from the Fixed Asset Purchasing Transactions window.

If you selected a purchasing transaction from the Fixed Asset Purchasing Transactions window, you can use the Asset Purchase window to enter or

change an acquisition cost, transaction description, currency ID, document number, and other information related to the purchase of the asset. You can enter more than one transaction for each asset.

7. Choose Save in the Asset General Information window.

If the originating unapplied value for a specific asset is zero cost or less, and Delete Purchasing Transactions Immediately is marked in the Fixed Assets Company Setup window, the transaction will no longer be displayed in the Fixed Asset Purchasing Transactions window.

Using Fixed Asset Management with Purchase Order Processing

You can create one or more asset records from a purchase order transaction displayed in the Fixed Assets Purchasing Transactions Display window until the total amount of the line item has been applied. The applied amount in the Fixed Assets Purchasing Transactions Display window will be updated when you choose Save in the Asset General Information window. You can view the information from the selected Purchase Order Processing transaction in the Asset Purchase window.

The Purchase Order Processing transaction is transferred to Fixed Asset Management when the transaction is posted. To transfer the transaction information when a specific account is selected, choose the by Account option in the Fixed Assets Company Setup window. To transfer specific line transaction information, choose the by Receipt Line option in the Fixed Assets Company Setup window.

By Account You must designate the accounts that will indicate the integration by entering them in the Post Accounts Setup window. When you create a purchase order, the account you enter on the receipt or the matching transaction must be an account set up in the Post Accounts Setup window.

By Receipt Line An asset record is created from an item when the receipt is posted. When you post a receipt, a separate integration record is created in Fixed Asset Management for each receipt line that's marked as a capital item in the Receivings Item Detail Entry window.

You can enter information tracked in the Asset General Information window for each receipt line when you enter receivings transactions in the FA PO Additional Information window. To transfer a transaction to Fixed Asset Management using a receipt with a matching invoice, the cost on the invoice must be different than the cost on the receipt. The amount of the difference will be the amount included in the transaction.

If you'll be receiving more than one item on the same receipt line (quantity is greater than 1), you can mark the Create Multiple Fixed Assets option in the FA PO Additional Information window to create a separate transaction for each item. A separate transaction will be created for each item with the acquisition cost equal to the unit cost of the item. Additional information entered in the FA PO Additional Information Window will be duplicated for each record.

If you're using landed costs, the landed costs that have been assigned to purchase order items or receivings line items will be transferred with the item cost when the purchase order transaction creates an asset record.

Integration options for Purchase Order Processing

The following table explains the effect that various options in the Fixed Assets Company Setup window, the FA PO Additional Information window, and the Receiving Item Detail Entry window have on the integration between Fixed Asset Management and Purchase Order Processing.

Window	Option	Effect marked option has
Fixed Assets Company Setup	by Account	The Purchase Order Processing transaction is transferred to the Fixed Assets Purchasing Transactions window when a receipt is posted. The transaction will be summarized by account for the entire receipt. Separate update transactions aren't created for each receipt line.
	by Receipt Line	The Purchase Order Processing transaction is transferred to the Fixed Assets Purchasing Transactions window only if you mark Capital Item in Purchase Order Processing when you enter the receipt transaction. If the Capital Item checkbox is marked on the purchase order, it will be marked on the receipt. The Capital Item checkbox will only appear if by Receipt Line is marked in the Fixed Assets Company Setup window
	Include Matching Invoices	Subsequent matching transactions also create additional fixed asset records for each receipt line matched with an invoice amount that varies from the receipt amount.
	Delete Purchasing Transactions immediately	Information in the Fixed Assets Purchasing Transactions window will be deleted when the total amount of the purchase transaction is applied by saving the total amount in the Asset Purchase window.
FA PO Additional Information	Create Multiple Fixed Assets	Creates a separate Fixed Asset Management transaction for each quantity. The unit cost is the amount of each transaction.
Receiving Item Detail Entry and Purchasing Item Detail Entry	Capital Item	Displays the Capital Item expansion button and transfers the Purchase Order Processing transaction to the Fixed Assets Purchasing Transaction window.

For more information about setting up the integration between Fixed Asset Management and Purchase Order Processing, refer to the following information:

- [Purchasing integration options](#) on page 24
- [Entering fixed assets posting accounts](#) on page 29
- [Deleting fixed assets purchasing transactions](#) on page 119

Adding asset records from Purchase Order Processing—by Account option

To enter assets in Purchase Order Processing and transfer them to Fixed Asset Management based on a specific General Ledger account number, mark the Post POP through to FA option in the Fixed Assets Company Setup window and select by Account. For more information, refer to [Purchasing integration options](#) on page 24.

If Post POP through to FA is marked in the Fixed Assets Company Setup window, you can create an asset record in Fixed Asset Management using information that's been entered in Purchase Order Processing.

The following table displays the information that's transferred to Fixed Asset Management from Purchase Order Processing.

From Purchase Order Processing	To Fixed Asset Management
Vendor ID	Vendor ID
Receipt Number	Control Number
Receipt Date	Acquisition Date
Receipt Date	Document Date
Vendor Document Number	Document Number
Transaction Source (RECVG Prefix)	Transaction Source
Distribution Reference or Receipt Reference	Description (Asset Purchase window)*
PURCH-Type Distribution Amounts	Acquisition Cost and Originating Acquisition Cost
*If there are multiple transactions, the primary transaction's voucher description will be displayed in the Asset Description field in the Asset General Information window.	

If the purchasing transaction uses Multicurrency Management, the following fields are transferred.

From Purchase Order Processing	To Fixed Asset Management
Currency ID	Currency ID
Currency Index	Currency Index
Exchange Rate	Exchange Rate
Exchange Date	Exchange Date
Time	Time
Exchange Table ID	Exchange Table ID
Rate Type ID	Rate Type ID
Rate Calc Method	Rate Calc Method
Denomination Exchange Rate	Denomination Exchange Rate
MC Trx State	MC Trx State

Use the Asset General Information window to create an asset record. Use the Fixed Assets Purchasing Transactions window to transfer information from transactions created in Purchase Order Processing to asset records in Fixed Asset Management.

To add asset records from Purchase Order Processing—by Account option:

1. Open the Asset General Information window.
(Cards >> Fixed Assets >> General)
2. Enter an asset ID and suffix.
3. Choose Purchase. The Purchase button is available only if there are transactions in the Fixed Assets Purchasing Transactions window.
4. In the Fixed Assets Purchasing Transaction window, mark the M box for each transaction to assign that transaction to the asset. Mark the P box for the primary transaction. Information from the primary transaction will be transferred to the asset record.
5. Choose Select to save the information from the selected transactions to the Asset General Information window and the Asset Purchase window.

6. In the Asset General Information window, enter any additional information.

You can enter an acquisition cost, currency ID, and originating acquisition cost in the Asset General Information window only if you haven't selected any purchasing transactions from the Fixed Asset Purchasing Transactions window.

If you selected a purchasing transaction from the Fixed Asset Purchasing Transactions window, you can use the Asset Purchase window to enter or change an acquisition cost, transaction description, currency ID, document number, and other information related to the purchase of the asset. You can enter more than one transaction for each asset.

7. Choose Save in the Asset General Information window.

If the originating unapplied value for a specific asset is zero cost or less, and Delete Purchasing Transactions Immediately is marked in the Fixed Assets Company Setup window, the transaction will no longer be displayed in the Fixed Asset Purchasing Transactions window.


Adding asset information after receiving purchasing transactions

You can enter additional information for that an asset in the FA PO Additional Information window before the Purchase Order Processing transaction is posted to General Ledger. You can open this window only if by Receipt Line is marked in the Fixed Assets Company Setup window. The information you enter in the FA PO Additional Information window will be displayed in the Asset General Information window.

To add asset information after receiving purchasing transactions:

1. Open the Receivings Transaction Entry window.
(Transactions >> Purchasing >> Receivings Transaction Entry)
2. Enter or select a receipt number and choose the Vendor Item expansion button to open the Receivings Item Detail Entry window.
3. Enter or select a vendor item.

4. Mark the Capital Item option and choose the Capital Item expansion button to open the FA PO Additional Information window.



5. Enter any information to be displayed in the Asset General Information window.
6. Choose Save.

Adding asset records from Purchase Order Processing –by Receipt Line option

To enter assets in Purchase Order Processing and transfer them to Fixed Asset Management by identifying specific transaction line items as capital items, mark the Post POP through to FA option in the Fixed Assets Company Setup window and select by Receipt. For more information, refer to [Purchasing integration options](#) on page 24.

If by Receipt line is marked in the Fixed Assets Company Setup window, you can create an asset record in Fixed Asset Management using information that’s been entered in Purchase Order Processing.

The following table displays the information that’s transferred to Fixed Asset Management from Purchase Order Processing.

From Purchase Order Processing	To Fixed Asset Management
Vendor ID	Vendor ID
POP Receipt Number	Control Number
Receipt Date	Document Date
Receipt Date	Acquisition Date
Vendor Document Number	Document Number
Transaction Source (RECVG Prefix)	Transaction Source
Purchase Order Type	Control Type
Item Description or Vendor Item Description	Description (Asset Purchase window)*
Purchase Order Number	Purchase Order Number
*If there are multiple transactions, the primary transaction’s voucher description will be displayed in the Asset Description field in the Asset General Information window.	

From Purchase Order Processing	To Fixed Asset Management
Quantity Shipped	Quantity
Extended Cost (Create Multiple Assets = No)	Acquisition Cost
Unit Cost (Create Multiple Assets = Yes)	Acquisition Cost
*If there are multiple transactions, the primary transaction's voucher description will be displayed in the Asset Description field in the Asset General Information window.	

If the purchasing transaction uses Multicurrency Management, the following fields are transferred.

From Purchase Order Processing	To Fixed Asset Management
Originating Extended Cost (Create Multiple Assets = No)	Originating Acquisition Cost
Originating Unit Cost (Create Multiple Assets = Yes)	Originating Acquisition Cost
Currency ID	Currency ID
Currency Index	Currency Index
Exchange Rate	Exchange Rate
Exchange Date	Exchange Date
Time	Time
Exchange Table ID	Exchange Table ID
Rate Type ID	Rate Type ID
Rate Calc Method	Rate Calc Method
Denomination Exchange Rate	Denomination Exchange Rate
MC Trx State	MC Trx State

If you're using Purchase Order Processing and the Include Matching Invoices option is marked in the Fixed Assets Company Setup window the same fields as the receipt will be updated in Fixed Asset Management except for the following fields:

From Purchase Order Processing	To Fixed Asset Management
Quantity Invoiced	Quantity
(Unit Cost – Receipt Cost) * Quantity Invoiced	Acquisition Cost
(Originating Unit Cost – Originating Receipt Cost) * Quantity Invoiced	Originating Acquisition Cost
Transaction Source	Transaction Source (POIVC Prefix)

The Include Matching Invoices option determines the difference between an invoice amount and a receipt amount.

Use the Asset General Information window to create an asset record. Use the FA PO Additional Information window to transfer information from Purchase Order Processing to asset records in Fixed Asset Management.

To add asset records from Purchase Order Processing—by Receipt Line option:

1. Open the Asset General Information window.
(Cards >> Fixed Assets >> General)
2. Enter or select an asset ID and suffix. If you entered the asset ID and suffix in the FA PO Additional Information window, you need to enter it now only if the Create Multiple Fixed Assets option in the FA PO Additional Information window is marked and you are retrieving the asset information to create an additional asset.
3. Choose Purchase. The Purchase button is available only if there are transactions in the Fixed Assets Purchasing Transactions window.
4. In the Fixed Assets Purchasing Transactions window, mark the M box for each transaction to assign that transaction to the asset. Mark the P box for the primary transaction. Information from the primary transaction will be transferred to the asset record.
5. Choose OK to save your changes in the Fixed Asset Purchasing Transactions window.
6. In the Asset General Information window, enter any additional information.

You can enter an acquisition cost, currency ID, and originating acquisition cost in the Asset General Information window only if you haven't selected any purchasing transactions from the Fixed Asset Purchasing Transactions window.

If you selected a purchasing transaction from the Fixed Asset Purchasing Transactions window, you can use the Asset Purchase window to enter or change an acquisition cost, transaction description, currency ID, document number, and other information related to the purchase of the asset. You can enter more than one transaction for each asset.

7. Choose Save in the Asset General Information window.

If the originating unapplied value for a specific asset is zero cost or less, and Delete Purchasing Transactions Immediately is marked in the Fixed Assets Company Setup window, the transaction will no longer be displayed in the Fixed Asset Purchasing Transactions window.

Using Fixed Asset Management with Multicurrency Management

You can use a currency other than the company's functional currency to record asset acquisitions and disposals. The functional currency will be calculated based on the appropriate exchange rates. If applicable, appropriate euro calculations will be made.

The following fields have multicurrency functionality:

Window name	Field name
Asset General Information	Acquisition Cost
Asset Purchase	Acquisition Cost
Retirements	Cash Proceeds
	Non-cash Proceeds
	Expenses of Sale
Mass Retirements	Cash Proceeds
	Non-cash Proceeds
	Expenses of Sale

If a multicurrency transaction originated in Payables Management or Purchase Order Processing, all appropriate exchange values will be transferred to Fixed Asset Management. Only the functional amount is saved with each asset book record and only functional amounts are transferred from Fixed Asset Management to General Ledger.

Mark the Multicurrency box in the Report Options window to print multicurrency versions of these reports:

- Additions report
- Additions by Class report
- Additions by Structure report
- Additions by Location report
- Retirements report
- Retirements by Class report
- Retirements by Structure report
- Retirements by Location report

Chapter 7: Asset import

If you have asset data in another fixed assets system or a different source, you can import asset records and balance information. You can import new asset records, asset book records, and insurance, lease, and user-defined information into Fixed Asset Management. You also can import information to make changes to the data for an existing asset record.

The following information is discussed:

- [*Guidelines for importing asset information*](#)
- [*Importing asset records*](#)
- [*Creating a new book record for existing assets*](#)
- [*Field mappings for importing asset information*](#)
- [*Field values*](#)

Guidelines for importing asset information

The following guidelines pertain to importing asset information into Fixed Asset Management from another source.

- If the value for a field contains a comma or a single quotation mark, the value must be enclosed in double quotation marks. For example: "Desk, 30x60, Walnut".
- You must create field setup information in Fixed Asset Management before you can import other asset information. The following field information must exist in Fixed Assets before you can import asset information:
 - Account group ID
 - Asset class ID
 - Book ID
 - Custodian (optional)
 - Insurance class
 - Lease company
 - Location ID
 - Physical location ID
 - Structure ID
- You must import information into the Asset General Information window before or with other information, but after the setup information is imported.
- If you use account numbers, be sure to mark the Required Accounts option in the Fixed Assets Company Setup window to save account numbers with the asset record.
- All numeric fields that have decimals are designated with the number of high-order digits and the number of decimal places. For example, '12.5' will allow an amount of 999,999,999,999.99999. You don't need to enter the decimal point or commas. If the value to the right of the decimal equals 0, enter all 0's or a decimal.
- If you enter any asset book information that would usually be displayed from the Book Class Setup window, the data displayed will not be default data from the Book Class table.

- Enter information in either both the Original Life Years field and the Original Life Days field, or neither field, to ensure accuracy.
- If you import information to a field that has a Fixed Asset Management default value, the information you import will replace the default information.
- When entering life-to-date depreciation in book records, be sure to include the amount in year-to-date depreciation. Year-to-date depreciation should be entered if the depreciated-to date represented by life-to-date depreciation is in the current fiscal year for the book, defined in the Book Setup window. Year-to-date depreciation is not required if the depreciated-to date is the last day of the current fiscal year.
- You can import only one asset purchase transaction for each asset.
- The import file must follow a specific format. The following table shows the required data to enter for each file.

Column A	Column B	Column C
Window identifier	Asset ID	Asset Suffix

For example, after importing the following information, you can view the information in the Asset General Information window. Three records will be created, but two of the records will have the same asset ID and different suffixes.

Column A	Column B	Column C
GENERAL	LIGHTTRUCK0005	1
GENERAL	LIGHTTRUCK0005	2

You must import information into specific columns. For information about field positions in the import file, refer to [Field mappings for importing asset information](#) on page 66. If you do not import data for an optional field, you must leave that column blank and not enter information for another field.

Importing asset records

You must mark the All Asset Info option in the Asset Import/Export window to import asset information or make changes to existing asset information.

When you import new asset information into the Asset General Information window, an asset book and financial detail information will be created for each book if the following conditions are met:


- The Auto Add Book Info option is marked in the Book Setup window for each book ID.
- The Auto Add Book Info option is marked in the Fixed Assets Company Setup window.

To import prior depreciation balances, unmark Auto Add Book Info for all Book Setup records in the Fixed Assets Company Setup window.

We recommend that you import several small files rather than one large file. You also should import the information to a test company to view the imported results.

To import asset records:

1. Open the Asset Import/Export window.
(Microsoft Dynamics GP menu >> Tools >> Utilities >> Fixed Assets >> Asset Import/Export)



2. Mark Import and select All Asset Info.
3. Enter or browse to find a location to create the macro in, and enter a file name for the macro. The file name extension should be .MAC.
4. Mark the Run Macro After Creation option to start the macro automatically after it is created. To run the macro later, from the Microsoft Dynamics GP menu choose Macro >> Play.
5. Enter or find the path and name of the file containing the data to be imported, or accept the default path and name—Asset.txt.
6. Select Comma- or Tab-delimited format.
7. Choose Continue to create the macro and import the data.

If a problem error occurs while running the macro that imports the data, information added prior to the problem does not have to be imported again.

Creating a new book record for existing assets

Use the Asset Import/Export window to create a new book record for an existing asset. You must export the existing asset ID and suffixes to a table. In the table, you can add the window identifier and the new book ID. When you import the modified table, asset book records will be created for the new book.



To create new book records you must first set up the book ID, class ID, and book class ID records. Refer to [Creating a book record](#) on page 14, [Creating a class record](#) on page 16, and [Creating a book class record](#) on page 21 for more information.

Be sure that the Auto Add Book Info option in the Fixed Assets Company Setup window is not marked when importing information to create asset books.

To create a new book record for existing assets:

1. Open the Asset Import/Export window.
(Microsoft Dynamics GP menu >> Tools >> Utilities >> Fixed Assets >> Asset Import/Export)
2. Mark Export and select Asset ID & Suffix.
3. Enter or find the location and name of the file to export the data to. Select Comma- or Tab-delimited format.
4. Choose Continue.
5. Open the exported file in Microsoft Excel® or Word. Edit the file to contain the window identifier—BOOK, Asset ID, Asset Suffix, and Book ID. The file name extension should be .TXT.
6. Import the file. For more information, refer to [Importing asset records](#) on page 64.

Field mappings for importing asset information

You can import data into multiple Fixed Asset Management tables. However, you cannot import data into any Fixed Asset Management setup tables.

The data that you import will be displayed in the following Fixed Asset Management windows:

- Asset General Information window
- Asset Book window
- Asset Lease window
- Asset Insurance window
- Asset User Data window

Asset General Information window fields

The following table displays the fields included in the Asset General Information window, their field types, length, and additional default entry information.

If you don't accept the default value for a field, you must supply a specific value for that field. For more information, refer to [Field values](#) on page 71.

Field name	Field type	Length	Default values	Required field
Window Identifier = GENERAL				Yes
Asset ID	String	15		Yes
Asset ID Suffix	Numeric	3	1	Yes
Short Name	String	15		No
Asset Description	String	40		Yes
Extended Asset Description	String	40		No
Master Asset ID	String	19		No
Account Group ID	String	15	From Asset Class	No
Structure ID	String	30		No
Asset Class ID	String	15		Yes
Location ID	String	15	From Phy Loc ID	No

Field name	Field type	Length	Default values	Required field
Acquisition Date	Date (MMDDYY or MMDDCCYY)	8	YY = System Year	Yes
Originating Acquisition Cost	Numeric	12.5		No
Asset Type	String	4	Refer to Field values on page 71 for more information.	Yes
Property Type	String	8	Refer to Field values on page 71 for more information.	Yes
Asset Quantity	Numeric	6	1	Yes
Current Maintenance Amount	Numeric	12.5		No
YTD Maintenance Amount	Numeric	12.5		No
LTD Maintenance Amount	Numeric	12.5		No
Last Maintenance Date	Date (MMDDYY or MMDDCCYY)	8	YY = System Year	No
Assessed Value	Numeric	12.5		No
Vendor ID	String	15		No
Document Number	String	20		No
Document Date	Date (MMDDYY or MMDDCCYY)	8	YY = System Year	No
Transaction Source	String	13		No
Control Number	String	20		No
Purchase Order Number	String	20		No
Document Description	String	40		No
Manufacturer Name	String	25		No
Serial Number	String	20		No
Model Number	String	20		No
Warranty Date	Date (MMDDYY or MMDDCCYY)	8	YY = System Year	No
Custodian (optionally requires setup)	String	25	15 is max length if validation is being used.	No
Physical Location ID	String	15		No
Asset Label	String	19		No
Verified Date	Date (MMDDYY or MMDDCCYY)	8	YY = System Year	No
PIN	String	15		No
Currency ID (Req'd only if registered for Multicurrency)	String	15	Functional Currency	Yes
Date Added	Date (MMDDYY or MMDDCCYY)	8	System Date	Yes

Asset Book window fields

The following table displays the fields included in the Asset Book window, their field types, length, and additional default entry information. If you don't accept the default value for a field, you must supply a specific value for that field. For more information, refer to [Field values](#) on page 71.

Field name	Field type	Length	Default values	Required
Window Identifier = BOOK				Yes
Asset ID	String	15		Yes
Asset ID Suffix	Numeric	3	1	Yes
Book ID	String	15		Yes
Place in Service Date	Date (MMDDYY or MMDDCCYY)	8	Acquisition Date on GI Or YY = System Year	Yes
Original Life Years	Numeric	2	From Book Class	No
Original Life Days	Numeric	3	From Book Class	No
Depreciated To Date	Date (MMDDYY or MMDDCCYY)	8	Place In Service Date or YY = System Year	Yes
Cost Basis	Numeric	12.5	Acquisition Cost on GI	No
Salvage Value	Numeric	12.5		No
Depreciation Method	String	5	Refer to Field values on page 71 for more information.	No
Averaging Convention	String	5	Refer to Field values on page 71 for more information.	No
Switchover	String	2	Refer to Field values on page 71 for more information.	No
Amortization Code	String	1	See Field values on page 71 for more information.	No
Amortization Amount/ Percentage	Numeric	12.5	From Book Class	No
YTD Depreciation Amount	Numeric	12.5		No
LTD Depreciation Amount	Numeric	12.5		No
Special Depreciation Allowance	String	3	Refer to Field values on page 71 for more information.	No
Special Depreciation Allowance Percentage	Numeric	3.2		No
Luxury Automobile Indicator	String	3	See Field values on page 71 for more information.	No
TEFRA Flag	String	5	See Field values on page 71 for more information.	No
ITC Amount Taken	Numeric	12.5		No
ITC Amount Allowed	Numeric	12.5		No
ITC Recapture	Numeric	12.5		No
Original Cost Basis	Numeric	12.5	From Book Cost Basis	No

Field name	Field type	Length	Default values	Required
Section 179 Expense Deduction	Numeric	12.5		No
ITC Cost Reduction Amount	Numeric	12.5		No
Miscellaneous Cost Adjustment	Numeric	12.5		No

Asset Lease window fields

The following table displays the fields included in the Asset Lease window, their field types, length, and additional default entry information. If you don't accept the default value for a field, you must supply a specific value for that field. For more information, refer to [Field values](#) on page 71.

Field name	Field type	Length	Default values	Required
Window Identifier = LEASE				Yes
Asset ID	String	15		Yes
Asset ID Suffix	Numeric	3	1	Yes
Lease Company	String	15		No
Lease Type	String	1	See Field values on page 71 for more information.	No
Lease Contract ID	String	15		No
Lease Payment	Numeric	12.5		No
Lease Interest Rate	Numeric	3.2		No
Lease End Date	Date (MMDDYY or MMDDCCYY)	8	YY = System Year	No

Asset Insurance window fields

The following table displays the fields included in the Asset Insurance window, their field types, length, and additional default entry information. If you don't accept the default value for a field, you must supply a specific value for that field. For more information, refer to [Field values](#) on page 71.

Field name	Field type	Length	Default	Required
Window Identifier = INS				Yes
Asset ID	String	15		Yes
Asset ID Suffix	Numeric	3	1	Yes
Insurance Class	String	15	From Asset Class	Yes
Insurance Year	Numeric	4		No
Insurance Value	Numeric	12.5		No
Replacement Cost	Numeric	12.5		No
Reproduction Cost	Numeric	12.5		No
Depreciated Reproduction Cost	Numeric	12.5		No
Exclusion Amount	Numeric	12.5		No
Exclusion Type	String	15		No

Asset User Data window fields

The following table displays the fields included in the Asset User Data window, their field types, length, and additional default entry information. If you don't accept the default value for a field, you must supply a specific value for that field. For more information, refer to *Field values* on page 71.

Field name	Field type	Length	Default value	Required
Window Identifier = USER				Yes
Asset ID	String	15		Yes
Asset ID Suffix	Numeric	3	1	Yes
User Field 1	String	6		No
User Field 2	String	6		No
User Field 3	String	10		No
User Field 4	String	10		No
User Field 5	String	20		No
User Field 6	String	20		No
User Field 7	String	20		No
User Field 8	String	20		No
User Field 9	String	40		No
User Field 10	String	40		No
User Field 11	Numeric	12.5		No
User Field 12	Numeric	12.5		No
User Field 13	Numeric	12.5		No
User Field 14	Numeric	12.5		No
User Field 15	Numeric	12.5		No

Field values

If you supply a value instead of accepting the default value for certain fields, you must supply a specific value for that field. The following table displays the values you can choose from when importing field information. For example, for the Asset Type field, to import the value Leased, import LSE. The window containing the field also is displayed.

Window name	Field name	Value	Enter
Asset General Information window	Asset Type	New	NEW
		Used	USED
		Leased	LES
	Property Type	Personal	PERS
		Personal, Listed	PERSLIST
		Real	REAL
		Real, Listed	RLISTED
		Real, Conservation	RCONS
		Real, Energy	REENERGY
		Real, Farms	REALFARM
		Real, Low Income Housing	REALLIH
		Amortizable	AMORT
Asset Lease window		Lease Type	Capital
	Operating		O
Asset Book window	Depreciation Methods	Straight-line Original Life	SLO
		Straight-line Remaining Life	SLR
		125% DB	125DB
		150% DB	150DB
		175% DB	175DB
		200% DB	200DB
		Sum of the Year's Digits	SOY
		Remaining Life	RL
		Amortization	AM
		ACRS Personal	AP
		ACRS Real	AR
		ACRS Real MSL	ARMSL
		ACRS LIH	ALIH
		ACRS Foreign Real	AF
		None	NONE
Declining Balance	DB		

Window name	Field name	Value	Enter
Asset Book window (continued)	Averaging Convention	Half Year	HY
		Modified Half Year	MHY
		Mid-Month (1st)	MM1st
		Mid-Month (15th)	MM15
		Mid-Quarter	MQ
		Next Month	NM
		Next Period	NP
		Full Month	FM
		Full Period	FP
		Next Year	NY
		Full Year	FY
		Full Year All Year	FYALL
		None	NONE
	Switchover	No Switch	NS
		Switch to Straight-Line	SL
	Amortization Code	Daily	D
		Weekly	W
		Monthly	M
		Quarterly	Q
		Yearly	Y
		Percentage	P
	Rate	Rate	R
	Luxury Automobile Indicator	Luxury Automobile	YES
		Not a Luxury Automobile	NO
	TEFRA Flag	None	NONE
		Full Credit Reduce Cost by 50%	FC50
		Full Credit Reduce Cost by 100%	FC100
		Reduce ITC% by 2 Points	RE
	Special Depreciation Allowance	Mark Special Depr Allowance	YES
		Unmark Special Depr Allowance	NO

Part 3: Asset records

This part of the documentation provides information about maintaining asset information. It also explains how to use asset groups to make maintaining asset records easier.

This part includes the following information:

- [Chapter 8, “Asset groups,”](#) describes asset groups and explains how to build and use the groups. It also explains how to add or remove assets from a group or delete a group.
- [Chapter 9, “Asset maintenance,”](#) explains how to change information for an asset or a group of assets and how to transfer asset information to a new general ledger account, property tax location, physical location, or structure.
- [Chapter 10, “Asset transfer,”](#) explains how to transfer an asset or a group of assets to a new general ledger account, property tax location, physical location, structure, or master asset ID.
- [Chapter 11, “Asset retirement,”](#) explains how to retire an asset, partially retire an asset, or retire a group of assets.

Chapter 8: Asset groups

You can group assets by specific characteristics and then use those groups to change, transfer, retire, or depreciate the assets in the groups. You also can use asset groups to project depreciation for the assets.

The following information is discussed:

- [Searching for assets](#)
- [Building an asset group](#)
- [Viewing assets in groups](#)
- [Importing data to create an asset group](#)
- [Deleting an asset group](#)
- [Removing assets from a group](#)

Searching for assets

Use the Asset Group Search window to select criteria from specific asset fields when building an asset group. Active assets that match the selection criteria will be included in the asset group. You can add additional assets to the group by building the asset group again with up to five different selection criteria.

To add an asset to the group, all field information must match the selection criteria, and then you must build the group using each set of criteria. The following examples explain the difference between the types of logic used to select assets.

“And” logic To build an asset group that includes all assets with the same asset ID and the same class ID, enter the following information in the Asset Group Search window. Assets with both the matching asset ID and the matching class ID will be displayed in the Select Assets window.

	Field Selection	Value	Action
1.	Asset ID	Equal	Enter or select an Asset ID.
2.	Class ID	Equal	Enter or select a Class ID.
3.	Choose Search. The results will be displayed in the Select Assets window.		

“Or” logic To build an asset group to include assets with either a specific asset ID or a specific class ID, enter the following information in the Asset Group Search window. Assets with the matching class ID will be displayed with the assets that have the matching asset ID.

	Field Selection	Value	Action
1.	Asset ID	Equal	Enter or select an Asset ID.
2.	Choose Search. The results will be displayed in the Select Assets window.		
3.	In the Select Assets window, choose Search.		
4.	Class ID	Equal	Enter or select a Class ID.
5.	Choose Search. The results of this search and the previous search will be displayed in the Select Assets window.		


Building an asset group

Use the Select Assets window to build a new asset group or rebuild an existing group. You can use asset groups to easily maintain assets.

Asset groups are saved on a user-by-user basis. For example, if user A creates an asset group, user B will not see that asset group anywhere in Fixed Asset Management.

To build an asset group:


1. Open the Select Assets window.
(Transactions >> Fixed Assets >> Select Assets)



2. To create and build a new group, choose New Group, enter a name to describe the asset group and choose OK.

If you're building an existing group, skip to step 3.

3. Select the group to build from the Current Group list and choose Search. The Asset Group Search window will open.



4. Select a field name and value, and then enter or select a specific field.

For example, to select assets that were placed in service before January 1, 2003, you would select Place in Service Date in the Field Selection field, Less Than in the Value field, and then enter 01/01/03.

5. Choose Search. All assets matching the selected values will be added to the group.

6. Repeat steps 3 through 5 to add additional assets to the group.
7. Choose OK to close the Select Assets window.

Viewing assets in groups

Use the Select Assets window to view assets that are part of an asset group. You can sort assets and select assets to view based on common characteristics or a range of information.

To view assets in groups:


1. Open the Select Assets window.
(Transactions >> Fixed Assets >> Select Assets)
2. Select a group in the Current Group list.
3. You can select to view all assets, assets that are in a selected group, or assets that aren't in a selected group.
4. You can select a sorting option to view assets by a specific characteristic, such as a location or class.
5. To view a range of assets, use the From and To fields to enter the range.
6. You can choose Mark or Unmark to include all assets or exclude all assets in the selected group.
7. Choose OK to close the window.

Importing data to create an asset group

Use the Select Assets window to import data to create an asset group. For example, you can import asset information for new assets with the same physical location ID from a source such as a bar code reader. The import file you use must be in either a comma- or tab-delimited format.

To import data to create an asset group:

1. Open the Select Assets window.
(Transactions >> Fixed Assets >> Select Assets)
2. Select an existing group or create a new group. To create a new group, refer to [Building an asset group](#) on page 75.
3. Choose Import Group to open the Import Group window.



4. Enter or locate the name of the file to import.
5. Choose a Save Option and choose how to import the data—by Asset ID or Asset Label.
6. Select a delimiter character.
7. Choose Continue and then choose OK to import the data and print the FA Asset Group Import report.

Deleting an asset group

Use the Select Assets window to delete an asset group. You also can remove an asset from the group. The assets in the group will not be deleted—only the asset group will be deleted.

To delete an asset group:

1. Open the Select Assets window.
(Transactions >> Fixed Assets >> Select Assets)
2. Select a group.
3. To remove an asset from the group, unmark the asset.
4. To delete the group, choose Delete Group and then Yes.
5. Close the window.

Removing assets from a group

Use the Select Assets window to remove all the assets from a group without deleting the group. See [Building an asset group](#) on page 75 to rebuild the group.

To remove assets from a group:

1. Open the Select Assets window.
(Transactions >> Fixed Assets >> Select Assets)
2. Select a group.
3. Choose Clear Group and then Yes.
4. Close the window.

Chapter 9: Asset maintenance

You can change information for an asset or group of assets. Some fields are depreciation-sensitive, which means that if you change the information in that field, depreciation needs to be recalculated.

The following information is discussed:

- [Changing asset information](#)
- [Recalculating depreciation](#)
- [Changing information for a group of assets](#)
- [Deleting an asset book record](#)
- [Calculating mid-quarter depreciation](#)

Changing asset information

Use the Asset General Information window to make changes to information in asset records and book records. You also can use this window to open other windows and make changes in those windows. If you change the cost basis of the asset, the Original Cost Basis field in the Asset Book ITC window will be adjusted by the amount of the change.

To change asset information:

1. Open the Asset General Information window.
(Cards >> Fixed Assets >> General)
2. Enter or select an asset ID and suffix.
3. If the information to be changed is displayed in this window, enter the new field information and choose Save.

To change information in other windows, refer to the following table for options:

Go To button option	Window that opens	Additional information
Account	Asset Account window	Refer to Modifying an asset account record on page 42 for more information.
Book	Asset Book window	Refer to Creating an asset book record on page 43 for more information.
Insurance	Asset Insurance window	Refer to Creating an asset insurance record on page 47 for more information.
Lease	Asset Lease window	Refer to Creating an asset lease record on page 48 for more information.
User Data	Asset User Data window	Refer to Creating an asset user-defined record on page 48 for more information.

4. If you change the Class ID in the Asset General Information window, the Reset Asset Class ID window will be displayed when you choose Save.

Book ID	Select Book(s)	Select one of the following options
AMT	<input type="checkbox"/> Propagate	<input checked="" type="radio"/> Recalculate <input type="radio"/> Reset Life <input type="radio"/> Reset Year
CORPORATE	<input type="checkbox"/> Propagate	<input checked="" type="radio"/> Recalculate <input type="radio"/> Reset Life <input type="radio"/> Reset Year
FEDERAL	<input type="checkbox"/> Propagate	<input checked="" type="radio"/> Recalculate <input type="radio"/> Reset Life <input type="radio"/> Reset Year

5. To update depreciation information in the books that the asset is associated with, mark the Propagate option, select what type of update to perform, and choose OK.



When you save changes to the Class ID in the Asset General Information window, the accounts associated with the new Class ID are also applied to the asset record. The changes are reflected in the Asset General Information and the Asset Account windows for the affected asset, even if you make no changes in the Reset Asset Class ID window.

Recalculating depreciation

When you make changes to specific fields in an asset book record, depreciation is recalculated. The following fields affect depreciation:

- Amortization Code
- Amortization Amount
- Averaging Convention
- Cost Basis
- Depreciation Method
- Depreciated To Date
- Life to Date Depreciation
- Luxury Automobile
- Original Life
- Place in Service Date
- Salvage Value
- Switchover
- Year to Date Depreciation
- Special Depr Allowance

There are three ways depreciation can be recalculated:

Reset Life Recalculates depreciation from the date it was placed in service through the date the asset already has been depreciated. Depreciation adjustments will be made for each period, but the depreciation does not have to be posted to General Ledger for each of these periods. You can use the Fixed Assets General Ledger Posting window to select a range of periods from the financial detail file, then post the entire amount to the period of the transaction date.

Reset Year Calculates a new yearly depreciation rate and uses the new rate to recalculate depreciation from the beginning of the current fiscal year—defined in the Book Setup window—through the date the asset already has been depreciated.

This depreciation does not have to be posted to General Ledger for each period. You can use the Fixed Assets General Ledger Posting window to select a range of periods from the financial detail file, then post the entire amount to the period of the transaction date.

Recalculate Calculates a new yearly depreciation rate as of the beginning of the current fiscal year defined in the Book Setup window. However, calculations are not based on the new rate until the next time depreciation is taken on the asset. The current year-to-date depreciation amount is not affected. The difference between the new yearly rate and the current year-to-date depreciation amount will be allocated over the remaining time in the current fiscal year.

- If an asset is in the first year of life (the Place in Service Date and Depreciated To Date are in the same fiscal year), and a depreciation-sensitive field other than Year-to-date Depreciation, Life-to-date Depreciation or Depreciated-to Date changes, the new rates for depreciation will be recalculated.
- If any of the following fields are changed—Year-to-date Depreciation, Life-to-date Depreciation, or Depreciated-to Date—depreciation will be recalculated, unless the Depreciated-to Date is the last day of the year.

Changing information for a group of assets

Use the Fixed Assets Mass Change window to change information for a group of assets. You must use a separate mass change process to change each type of asset record. For example, to change asset general information and asset account information, you must complete two mass changes. If information for an asset doesn't exist, the mass change process will not create the information. You also must build a new asset group before each mass change process. Asset groups are built based on the assets on file when the group is created. Refer to [Building an asset group](#) on page 75 for more information.

The Fixed Assets Mass Change window has four tabs. You can refer to the following information about the tabs when changing asset information:

General If you change the Asset Class ID, only the class ID in the Asset General Information window will be changed. To change book class information, such as depreciation characteristics, you also must make a mass change for the asset group, using the Book tab.

Account You can select an account group. The accounts set up for that account group will appear as default entries in the account fields in this window. You can mark the accounts to change.


Book You can change book class information. All of the fields are depreciation-sensitive. When any depreciation-sensitive fields change, you must indicate whether the changes should take effect from the date the asset is currently depreciated (Recalc Remaining), as of the beginning of the current fiscal year (Reset Year) or as of the Place in Service Date (Reset Life). Refer to [Recalculating depreciation](#) on page 80 for more information.

If you changed the Asset Class ID using the General tab, you also must make a mass change for the asset group using the Book tab to change book class information, such as depreciation characteristics.

User You can change any information for user-defined fields. You also can select default values to be used.

To change information for a group of assets:

1. Open the Fixed Assets Mass Change window.
(Transactions >> Fixed Assets >> Mass Change)



2. Select an asset group ID and choose a tab—General, Account, Book, User.
3. Mark the fields to be changed and enter or select the new values.
4. Choose Apply Changes to change the information.
5. To make additional changes to this asset group, repeat steps 2 through 4 for each mass change.
6. Choose OK to close the Mass Change window.

Deleting an asset book record

Use the Asset Book window to delete an asset book record. You also must make General Ledger entries to reverse any cost or depreciation that has been posted for this asset. For more information, refer to the General Ledger documentation.

To delete an asset book record:

1. Open the Asset Book window.
(Cards >> Fixed Assets >> Book)
2. Enter or select an asset ID and suffix.
3. Enter or select a book and choose Delete. The book and all the financial detail of the book will be deleted.

Calculating mid-quarter depreciation

If more than 40% of the total cost of assets purchased during the current year were purchased in the last quarter of the year, you must use the mid-quarter averaging convention to calculate depreciation for US federal income tax purposes for personal property placed in service that year. Print the Mid-Quarter Applicability report to determine the total cost of assets purchased each quarter of any year.

Use the Mass Change window to calculate mid-quarter depreciation. You must create a group of assets purchased in the current fiscal year before you can calculate mid-quarter depreciation. Refer to [Building an asset group](#) on page 75 for more information.

To calculate mid-quarter depreciation:

1. Open the Mass Change window.
(Transactions >> Fixed Assets >> Mass Change)
2. Choose the Book tab and select an asset group ID.
3. Enter or select the tax book in the Book ID field.
4. Mark the Averaging Convention option and select Mid-Quarter.
5. Select the Reset Life option.
6. Choose Apply Changes.

Chapter 10: Asset transfer

You can transfer an asset or a group of assets to a new general ledger account, property tax location, physical location, structure, or master asset ID.

When you transfer an asset or group of assets, depreciation will be calculated through the transfer date using the current account numbers. Depreciation using the new account numbers will begin on the day after the transfer date. If the transfer date is earlier than the date through which the asset has been depreciated, depreciation will be backed out to the transfer date using the current account numbers.

The following information is discussed:


- [*Transferring asset record information*](#)
- [*Partially transferring an asset*](#)
- [*Transferring multiple assets*](#)

Transferring asset record information

Use the Transfer Maintenance window to transfer an asset to a new General Ledger account, property tax location, physical location, structure, or master asset ID for an individual asset.

To transfer asset record information:

1. Open the Transfer Maintenance window.
(Transactions >> Fixed Assets >> Transfer)



2. Enter or select an asset ID. Only active assets—assets that are not retired—can be transferred.
3. Enter the transfer date. The transfer date must be in the current fiscal year.
4. Enter or select the new asset information. Choose the G/L Accounts expansion button to open the Expand Transfer window and enter or select new account numbers. Do not delete account numbers that are not changing.

5. Choose Transfer and verify the transfer results using the Transfer Inquiry, Asset Book Inquiry, or Financial Detail Inquiry windows. The Transfer Report can also be printed. A separate audit record that you can print is created each time an asset is transferred.

Partially transferring an asset

Use the Transfer Maintenance window to partially transfer an asset. You can partially transfer an asset based on quantity, cost, or a percentage. After you partially transfer an asset, a new asset is created with the same asset ID as the original asset and an incremental suffix.

A partial transfer of an asset can be based on one of the following options:

Quantity The quantity to transfer. The transfer quantity will be divided by the quantity in the Asset General Information record to determine a transfer percentage. The percentage will be applied to all amount fields in every asset record—asset general information, asset purchase, asset book, asset book/ITC, asset lease, asset insurance, and asset user data—associated with the asset you're transferring. If the asset is being transferred to more than one place, the total of all transfer quantity entries cannot exceed the quantity in the Asset General Information window.

Cost The cost to transfer. The transfer cost must be equal to or less than the cost on any book for the asset being transferred. The transfer cost will reduce the cost of the corporate book record. A transfer percentage will be calculated by dividing the transfer cost by the cost basis in the corporate book. This percentage will be applied to all amount fields in every asset record—asset general information, asset purchase, asset book, asset book/ITC, asset lease, asset insurance, and asset user data—associated with this asset. You can base a partial asset transfer on cost only if a corporate book exists for the asset being transferred. Also, the total of all transfer cost entries cannot exceed the cost basis on the book record for any book for the asset being transferred.

Percent The percentage to transfer. The percentage will be applied to all amount and quantity fields related to the asset. The total of all transfer percentage entries cannot exceed 100%.

If you enter a combination of transfer quantity and transfer percentage, the transfer percentage will be applied to each dollar field associated with the asset being transferred. If you enter a transfer quantity and a transfer percentage and the transfer percentage is not the same percentage that is calculated by dividing quantity in the Asset General Information record by the transfer quantity, the percentage you entered will be changed.

If you enter a combination of transfer quantity and transfer cost, the transfer quantity will reduce the quantity in the Asset General Information window and the transfer cost will be divided by the cost basis on the corporate book.

Each line related to the partial transfer must have the same combination of field entries. For example, if only transfer percentage is entered on one line of the partial transfer, then only transfer percentage can be entered on subsequent lines.

To partially transfer an asset:

1. Open the Transfer Maintenance window.
(Transactions >> Fixed Assets >> Transfer)
2. Enter or select an asset ID. Only active assets—assets that are not retired—can be transferred.
3. Enter the transfer date. The transfer date must be in or before the current fiscal year.
4. Enter the partial transfer information. For more information, refer to [Partially transferring an asset](#) on page 86.
5. You can enter or select new asset information, if necessary.
6. Choose Transfer and verify the transfer results in the Transfer Inquiry, Asset Book Inquiry, or Financial Detail Inquiry windows.

Transferring multiple assets

Use the Fixed Assets Mass Transfer window to transfer a group of assets to a different property tax location, physical location ID, structure ID, master asset ID, or change General Ledger account numbers. Before you can transfer a group of assets, you must first define an asset group in the Select Assets window. Refer to [Building an asset group](#) on page 75 for more information.



Be sure to build a new asset group before each mass transfer. If you transfer multiple assets for an existing asset group, it's possible that not all assets that you intend to transfer will be transferred.

To transfer multiple assets:

1. Open the Fixed Assets Mass Transfer window.
(Transactions >> Fixed Assets >> Mass Transfer)

Account Group ID					
Depr Expense	-	-	-	-	
Depr Reserve	-	-	-	-	
Prior Year Depr	-	-	-	-	
Asset Cost	-	-	-	-	
Proceeds	-	-	-	-	
Rec. Gain/Loss	-	-	-	-	
Non Rec. Gain/Loss	-	-	-	-	
Clearing	-	-	-	-	

2. Select an asset group ID.
3. Enter the transfer date. The transfer date must be in the current fiscal year.

4. Enter or select the new asset information.
5. You can enter or select an account group ID to view the existing account numbers and enter or select new account numbers for the assets. The account numbers displayed when you choose Transfer will be used to update each asset being transferred.
6. Choose Transfer.
7. Close the Mass Transfer window.

Chapter 11: Asset retirement

You can retire an asset, partially retire an asset, or retire a group of assets. The retirement date you enter will be used to calculate the prorated amount of depreciation allowed for each book for each asset based on the averaging convention. Depreciation can be calculated forward or backward from the depreciated-to date to the prorated retirement date based on the rules for the averaging convention being used.

If you're using Multicurrency and you select a currency ID different than the functional currency defined for this company, the functional currency will be used to calculate the cash proceeds, non-cash proceeds, and expenses of sale, based on the exchange rate.

The following information is discussed:

- [*Retirement proceeds and expenses*](#)
- [*Recording the sale or disposal of an asset*](#)
- [*Partially retiring an asset*](#)
- [*Reversing a retired asset record*](#)
- [*Using retirement spread options*](#)
- [*Recording the sale or retirement of a group of assets*](#)

Retirement proceeds and expenses

When you retire an asset record using the Retirement Maintenance window, you must enter the proceeds and expenses related to the retirement of that asset. You can enter information in each of the following options:

Cash proceeds The dollar amount received for an asset when it was sold.

Non-cash proceeds The dollar value of anything not in the form of cash that you received for an asset, such as a similar asset you received in exchange.

Expenses of sale The amount it cost you to sell an asset.

After you retire an asset record, choose the Prorated Retire Date expansion button in the Asset Book Inquiry window to view the gain/loss calculations. The following gain/loss values will be calculated using the proceeds and expense information, net book value, and retirement type for the asset:

Gain/Loss Method	Retirement Type	Calculation
Realized Gain/Loss		Cash Proceeds + Non-Cash Proceeds - Expenses of Sale - Net Book Value
Positive and less than or equal to Cash Proceeds	Like Kind Exchange	Recognized Gain/Loss will contain the amount calculated for Realized Gain/Loss
Positive and greater than Cash Proceeds	Like Kind Exchange	Recognized Gain/Loss will contain the amount in Cash Proceeds and Non-Recognized Gain/Loss is equal to Realized Gain/Loss - Cash Proceeds
Realized Gain/Loss is negative	Like Kind Exchange	Non-Recognized Gain/Loss will contain the amount calculated for Realized Gain/Loss
Realized Gain/Loss is positive	Involuntary Conversion	Non-Recognized Gain/Loss will contain the amount calculated for Realized Gain/Loss if books other than the corporate books


Gain/Loss Method	Retirement Type	Calculation
Calculation used in all other cases, and when the above conditions are not met.		Recognized Gain/Loss will contain the amount calculated in Realized Gain/Loss

Recording the sale or disposal of an asset

Use the Retirement Maintenance window to record the sale or disposal of an individual asset. The averaging convention for the asset will be used to determine how much depreciation is allowed in the year of retirement. Gain and loss are calculated for each book record, using the proceeds, expenses of sale, and retirement type entered in the Retirement Maintenance window, and the net book value displayed in the Asset Book window.

To record the sale or disposal of an asset:

1. Open the Retirement Maintenance window.
(Transactions >> Fixed Assets >> Retire)



2. Enter or select an asset ID and suffix. Only active assets can be retired.
3. Enter a retirement date and select a retirement type to classify the disposal. The retirement type determines the classification of the gain and loss calculation as recognized or non-recognized.
4. You can enter or select a retirement code to further describe the retirement.
5. Enter the proceeds and expenses of sale, if any, related to the retirement of the asset.
6. Choose Retire. You can view the results using the Retirement Inquiry, Asset Book Inquiry, or Financial Detail Inquiry windows.

Partially retiring an asset

Use the Retirement Maintenance window to partially retire an asset. You can base a partial retirement on quantity, cost, or a percentage of the asset. After you partially retire an asset, a new asset record is created using the same asset ID of the asset retired and an incremental suffix.

A partial retirement of an asset can be based on one of the following options:

Quantity The quantity to retire. A retirement percentage will be calculated by dividing the retirement quantity by the quantity on the Asset General Information record and then rounding. This percentage will be applied to all dollar fields in every asset record—asset general information, asset purchase, asset book, asset book ITC, asset lease, asset insurance, and asset user data—associated with the asset you’re retiring. If the asset is being retired in more than one piece, the total of all retirement quantity entries cannot exceed the quantity in the Asset General Information window.

Cost The retirement cost. The cost will be used to reduce the cost on the corporate book record and must be less than the cost on the corporate book record for the asset being retired. For each book record other than the corporate book, a retirement percentage will be calculated by dividing the retirement cost by the cost basis on the corporate book. This percentage will be applied to all dollar fields in every asset record—asset general information, asset purchase, asset book, asset book ITC, asset lease, asset insurance, and asset user data—associated with this asset. You can base a partial asset retirement on cost only if a corporate book exists for the asset being retired. In addition, the total of all retirement cost entries cannot exceed the cost basis on the any book for the asset being retired.

Percent The retirement percentage to be applied to all dollar fields related to this asset. Each line related to the partial retirement must have the same combination of field entries. For example, if only retirement percentage is entered on the first line of a partial retirement, then only retirement percentage can be entered on subsequent lines. The total of all retirement percentage entries cannot exceed 100%.

If you enter a combination of retirement quantity and retirement percentage, the retirement percentage will be applied to each dollar field associated with the asset being retired. If you enter a retirement quantity and a retirement percentage, and the percentage is not the same percentage that is calculated by dividing the quantity in the asset general information record by the retired quantity, the percentage you entered will be changed.

If you enter a combination of retirement quantity and a retirement cost, the retirement quantity will reduce the quantity in the Asset General Information window and the retirement cost will be divided by the cost basis on the corporate book.

Each line related to the partial retirement must have the same combination of field entries. For example, if only retirement percentage is entered on one line of the partial retirement, only retirement percentages can be entered on subsequent lines.

To partially retire an asset:

1. Open the Retirement Maintenance window.
(Transactions >> Fixed Assets >> Retire)
2. Enter or select an asset ID and suffix. Only active assets can be retired.
3. Enter a retirement date and select a retirement type to classify the disposal. The retirement type determines the classification of the gain and loss calculation as recognized or non-recognized.
4. You can enter or select a retirement code to further describe the retirement.

5. Enter partial retirement information. Enter the proceeds and expenses of sale, if any, related to the retirement of the asset.
6. Choose Retire. You can view the results using the Retirement Inquiry, Asset Book Inquiry, or Financial Detail Inquiry windows.


Reversing a retired asset record

Use the Retirement Undo window to reverse a retired asset record. You can reactivate a retired asset record if an incorrect asset was retired or if incorrect proceeds were entered. To reverse a partially retired asset, the original asset must still be active. If the asset isn't active, you must reactivate it.

Reactivating the asset puts the asset back to its original state before it was retired. Any financial detail records that were created as a result of the retirement will be reversed.

To reverse a retired asset record:

1. Open the Retirement Undo window.
(Transactions >> Fixed Assets >> Retire Undo)



2. Enter or select an asset ID and suffix. Only asset records that were retired during the current fiscal year can be reactivated.
3. Choose Undo to reactivate the asset record.

Using retirement spread options

When you retire multiple asset records using the Fixed Assets Mass Retirement window, you must select a spread option to account for cash proceeds, non-cash proceeds, and expenses of sale. A spread accounts for the allocation of proceeds and expenses of sale for selected assets when retiring those assets. You can choose from the following four spread options:

Use this amount for each asset The amount entered in the Cash Proceeds, Non-Cash Proceeds, and Expenses of Sale fields will be used when retiring each asset.

Average evenly over each asset The amount entered in the Cash Proceeds, Non-Cash Proceeds, and Expenses of Sale fields will be divided by the number of assets in the asset group being mass-retired. This amount will be used to retire each asset. If the amounts don't divide evenly, any remainder will be applied to the last asset in the asset group when it's retired.

As a percentage of corporate cost The sum of the corporate cost for all assets in the asset group being mass-retired will be calculated. The cost basis of each asset in the group will be divided by this total to determine its percentage of the total net book value. Each percentage of each asset will be separately multiplied by

the total amount in the Cash Proceeds, Non-Cash Proceeds, and Expenses fields to determine the amount of each that applies to this asset.

Suppose you enter the following values:

- Cash Proceeds = \$3,000
- Non-Cash proceeds = \$1,500
- Expenses of Sale = \$500

In the asset group there are three assets:

- Asset 1 corporate cost basis = \$5,000
- Asset 2 corporate cost basis = \$1,000
- Asset 3 corporate cost basis = \$4,000

The total cost basis equals \$10,000, and the allocation for asset 1 is 50% ($\$5,000 \div \$10,000 = 50\%$). Therefore, the following amounts will be allocated for asset 1:

- Cash proceeds: $\$3,000 \times 50\% = \$1,500$
- Non-cash proceeds: $\$1,500 \times 50\% = \750
- Expenses of sale: $\$500 \times 50\% = \250

As a percentage of corporate net book value The sum of the corporate net book value for all assets in the asset group being mass-retired will be calculated. The net book value of each asset in the group will be divided by this total to determine its percentage of the total net book value. Each percentage of each asset will be separately multiplied by the total amount in the Cash Proceeds, Non-Cash Proceeds, and Expenses fields to determine the amount of each that applies to this asset.

Suppose you enter the following values:

- Cash Proceeds = \$2,000
- Non-Cash proceeds = \$2,000
- Expenses of Sale = \$3,000

In this asset group there are three assets:

- Asset 1 corporate net book value = \$1,000
- Asset 2 corporate net book value = \$4,000
- Asset 3 corporate net book value = \$5,000

The total net book value equals \$10,000, and asset 1's allocation is 10% ($\$1,000 \div \$10,000 = 10\%$). Therefore, the following amounts will be allocated for asset 1:

- Cash proceeds: $\$2,000 \times 10\% = \200
- Non-cash proceeds: $\$2,000 \times 10\% = \200
- Expenses of sale: $\$3,000 \times 10\% = \300

Recording the sale or retirement of a group of assets

Use the Fixed Assets Mass Retirement window to record the sale or disposal of a group of assets. You must build a new asset group for each mass retirement to ensure that all existing assets that meet the criteria selected are included in the retirement. For more information, refer to [Building an asset group](#) on page 75.

To record the sale or retirement of a group of assets:

1. Open the Fixed Assets Mass Retirement window.
(Transactions >> Fixed Assets >> Mass Retire)

2. Select an asset group ID.
3. Enter a retirement date and select a retirement type.
4. You can enter or select a retirement code to describe why the assets are being retired.
5. Enter or select a currency ID if the currency is different from the functional currency ID.
6. Enter the cash proceeds, non-cash proceeds, and expenses of sale. These amounts will be used when retiring each asset in the asset group.
7. Choose a spread option, or accept the default option. Refer to [Using retirement spread options](#) on page 92 for more information.
8. Choose Retire.
9. Close the Fixed Assets Mass Retirement window.

Chapter 12: Asset depreciation

Depreciation is the allocation of the cost of an asset over a period of time for accounting and tax purposes. You can calculate depreciation or a projected depreciation amount for an individual asset, for a group of assets, or for all assets.

For more information about various methods of depreciation and a description of them, refer to [Depreciation methods and calculations](#) on page 17.

US tax luxury automobile limits are provided, as well as tables for ACRS (Accelerated Cost Recovery System) personal property, ACRS real estate based on the 175% declining balance method, ACRS real estate using modified straight-line, ACRS low income housing, and ACRS foreign real property. MACRS (Modified Accelerated Cost Recovery System) depreciation is calculated using formulas.



Back up your Fixed Asset Management data before beginning any depreciation process.

The following information is discussed:

- [Depreciating one asset](#)
- [Depreciating assets in one or more books](#)
- [Recalculating depreciation for an asset](#)
- [Reversing depreciation for an asset](#)
- [Projecting depreciation for one asset](#)
- [Projecting depreciation for assets in one or more books](#)


Depreciating one asset

Use the Depreciate Asset window to depreciate an asset in a book. You also can recalculate depreciation, if necessary. The depreciation target date must be within a fiscal year that is set up in the Fiscal Periods Setup window and must be in the current fiscal year defined in the Book Setup window.

Depreciation is calculated for each asset for each period included in the depreciation process. In General Ledger, the depreciation expense account is debited and the depreciation reserve account is credited.

To depreciate one asset:

1. Open the Depreciate Asset window.
(Microsoft Dynamics GP menu >> Tools >> Routines >> Fixed Assets >> Depreciate One Asset)



2. Enter or select the asset ID and suffix of the asset to be depreciated.
3. Enter the depreciation target date.
4. Select a book and choose Depreciate.

Depreciating assets in one or more books


Use the Depreciation Process Information window to depreciate asset groups in specific books or all assets set up in Fixed Asset Management. For more information about asset groups, refer to [Building an asset group](#) on page 75.

The target date fiscal year must be set up in the Fixed Assets Fiscal Periods file and can't be later than the Current Fiscal Year entered in the Book Setup window for every book selected to be depreciated.

Depreciation is calculated for each asset for each period included in the depreciation process. In General Ledger, the depreciation expense account is debited and the depreciation reserve account is credited.

To depreciate assets in one or more books:

1. Open the Depreciation Process Information window.
(Microsoft Dynamics GP menu >> Tools >> Routines >> Fixed Assets >> Depreciate)



2. To depreciate an asset group, unmark Depreciate all assets and select an asset group ID. To depreciate all active assets—assets that are not fully depreciated—in the selected books, mark Depreciate all assets.
3. Enter the depreciation target date. All active assets in this company that haven't already been depreciated to the depreciation target date will be depreciated through this date.
4. Select the books to be depreciated and choose Depreciate.
5. Close the window.

Recalculating depreciation for an asset

Use the Depreciate Asset window to recalculate depreciation for an asset when you don't need to change a depreciation-sensitive field in the Asset Book window for an asset.

To recalculate depreciation for an asset:

1. Open the Depreciate Asset window.
(Microsoft Dynamics GP menu >> Tools >> Routines >> Fixed Assets >> Depreciate One Asset)
2. Enter or select an asset ID and suffix.
3. Enter the depreciation target date. Do not enter a date to recalculate depreciation as of the first day of the current fiscal year (Reset Year) or as of the date the asset was placed in service (Reset Life).
4. Select a book and choose Depreciate.
5. Choose Reset Year to recalculate depreciation as of the first day of the Current Fiscal Year defined on the Book Setup.

Choose Reset Life to recalculate depreciation as of the Place in Service Date of the asset.

Both Reset Year and Reset Life will recalculate depreciation forward to the date through which the asset was previously depreciated. You can not enter a depreciation target date when either of these two options is selected.

6. Close the window.

Reversing depreciation for an asset

You can reverse depreciation for an asset by entering a target date that is before the date through which the asset book has been depreciated. The target date cannot be before than the first day of the current fiscal year defined in the Book Setup window for the book being depreciated.

Use the Depreciate Asset window to reverse depreciation for an asset.

To reverse depreciation for an asset:

1. Open the Depreciate Asset window.
(Microsoft Dynamics GP menu >> Tools >> Routines >> Fixed Assets >> Depreciate One Asset)
2. Enter the asset ID and suffix of the asset to reverse depreciation for.
3. Enter the depreciation target date. This date must be before the date through which the asset book has been depreciated
4. Select a book and choose Depreciate.
5. Close the window

Projecting depreciation for one asset

You can calculate a projected depreciation amount without updating the asset book or the financial detail tables. The calculations for depreciation projections are identical to those for an actual depreciation; however, book and financial detail information is not updated. A separate depreciation amount is projected for each fiscal period projected. Because projected depreciation amounts are saved by user ID, each user can project depreciation without affecting another user's depreciation projections.

Use the Depreciate Asset window to project depreciation for one asset in a book. When the projection process is finished, you can print projection reports or view projection information in an inquiry window.

To project depreciation for one asset:


1. Open the Depreciate Asset window.
(Microsoft Dynamics GP menu >> Tools >> Routines >> Fixed Assets >> Depreciate One Asset)
2. Enter or select an asset ID and suffix.
3. Enter the date to project depreciation through in the Depreciation Projection Target date field.
4. Select a book and mark the Projection Only option.
5. Choose Depreciate and close the window.
6. View the information in the Projection Inquiry window. For more information, refer to [Viewing projected depreciation information](#) on page 140.

Projecting depreciation for assets in one or more books

Use the Depreciation Projection window to project depreciation for assets in one or more books. We recommend that you project depreciation several years forward for all books. You can print projection reports for specific years or periods.

To project depreciation for assets in one or more books:

1. Open the Depreciation Projection window.
(Microsoft Dynamics GP menu Routines >> Fixed Assets >> Projection)



2. To project depreciation for an asset group, unmark Project all assets and select an asset group ID. Otherwise, leave Project all assets marked to project depreciation for all assets.

For more information, refer to [Building an asset group](#) on page 75.

3. Enter the date to project depreciation through in the Depreciation Projection Target date field.
4. Select a book and choose Insert to move the book to the Selected Books list.
5. Choose Projection and close the window.
6. You can print projection reports or view the information in the Projection Inquiry window. For more information, refer to [Viewing projected depreciation information](#) on page 140.

Part 4: Routines

This part of the documentation provides information about procedures you can use to calculate depreciation of your assets. It also includes information about year-end processes you can use and how you can integrate Fixed Asset Management with General Ledger.

This part includes the following information:

- [Chapter 12, “Asset depreciation,”](#) explains how you can use various depreciation methods to calculate depreciation for an individual asset, for a group of assets, or for all the assets in one or more books. You also can project depreciation amounts without changing asset information.
- [Chapter 13, “Year-end processes,”](#) describes the various routines you can use at the end of a fiscal year to close books and summarize and clear data.
- [Chapter 14, “General Ledger integration,”](#) explains how to use a routine to integrate Fixed Asset Management data with General Ledger.
- [Chapter 15, “Physical inventory,”](#) explains how to reconcile the actual physical location for an asset to the physical location ID entered for the asset. It also explains how to identify missing or misplaced assets by using the physical inventory reconciliation process.

Chapter 13: Year-end processes

You can close a Fixed Asset Management fiscal year to update depreciation amounts, summarize financial data, and remove inactive asset record information.

Once you've closed the fiscal year, you cannot print reports for the prior year. You should print reports that include year-to-date depreciation for your assets before closing the fiscal year. You also can maintain Fixed Asset data tables by summarizing historical detail information, and deleting inactive asset records when it is no longer necessary to store the information.

Before you can close the fiscal year, you must complete the following tasks:

- Enter all activity for the current fiscal year, including asset additions, changes, transfers, and retirements.
- Process asset depreciation for the final period, through the last day, of the current fiscal year.
- Post transactions to General Ledger.
- Post the General Ledger batch.
- Process year-to-date depreciation and print activity reports.
- Make a backup of your data.

To close the fiscal year, you must close the asset books and verify data after the books are closed.

You also can summarize financial detail data and delete inactive asset records.

If the fiscal periods for the new year in the Microsoft Dynamics GP fiscal calendar have been changed since the Fixed Asset Management calendar was last built, you should rebuild the Fixed Asset Management fiscal calendar for future years. You should do this only after you run the year-end process.

The following information is discussed:

- [Closing the asset books](#)
- [Summarizing financial data](#)
- [Deleting inactive asset information](#)

Closing the asset books

At the end of each fiscal year, you can update depreciation amounts. The year-end routine increases the current fiscal year by one year for each book that is being closed and changes the Year-to-Date Depreciation Amount and YTD Maintenance Amount fields to zero. Also, the values in specific fields are copied to other fields. The following fields are changed when you close your asset books:

Window	Field information is copied from	Field information is copied to
Asset Book	Cost Basis	Begin Cost
Asset Book	Life-to-Date Depreciation Amount	Begin Reserve
Asset General Information	Quantity	Begin Quantity
Asset Book	Salvage	Begin Salvage




Back up your data before closing asset books.

Before you begin, be sure that no other users are running any other processes in Fixed Assets, such as depreciation. Users can use other modules in Microsoft Dynamics GP while you are closing the asset books.

Use the Asset Year End window to process the year-end routine.

To close the asset books:

1. Open the Asset Year End window.
(Microsoft Dynamics GP menu >> Tools >> Routines >> Fixed Assets >> Year End)




2. Select each book to be closed and choose Insert.
3. Choose Continue.
4. Choose Continue again and close the window.

Summarizing financial data

You can summarize financial data by asset record, book record, transaction account type, and specific periods at any time during the year. Summarizing asset data frees up hard disk space and is typically done at the end of the fiscal year. Once records have been summarized, you can no longer view detailed information. Use the Asset Financial Detail Summarize window to summarize financial data.

To summarize financial data:

1. Open the Asset Financial Detail Summarize window.
(Microsoft Dynamics GP menu >> Tools >> Routines >> Fixed Assets >> Summarize Financial)




2. Enter the beginning and ending period ranges of records to be summarized.
3. Choose OK and close the window. The Financial Detail Summary report will be printed.

Deleting inactive asset information

You can delete information for inactive—deleted, retired, or partially open—assets. Deleting asset data frees up hard disk space and is typically done at the end of the fiscal year. You should only delete data from a prior year. Use the Asset Purge window to delete asset information.

To delete inactive asset information:

1. Open the Asset Purge window.
(Microsoft Dynamics GP menu >> Tools >> Routines >> Fixed Assets >> Purge)



2. Enter the Purge Prior to Date. All information for inactive asset records with a retirement date or a delete date before this date will be deleted.
3. Mark the asset statuses to delete asset records with those statuses.
4. Choose Purge and then Continue. The FA Purge report will be printed.

Chapter 14: General Ledger integration

You can use a routine to integrate Fixed Asset Management data with General Ledger. The Fixed Assets GL Posting routine creates a batch of transactions—which includes one General Ledger journal entry—that you can post to General Ledger. You can select the data to post in the Fixed Assets General Ledger Posting window. The General Ledger journal entry is in summary format by General Ledger account numbers. The batch number will have the prefix FATRX, followed by a sequential number.

Use the Fixed Assets to General Ledger Reconciliation report to reconcile Fixed Asset Management periodic activity to General Ledger. You can mark the Only Not Posted option for this report to view the Fixed Asset amounts that will be posted to General Ledger.

The following information is discussed:


- [*Migrating from another fixed assets system*](#)
- [*Updating General Ledger with Fixed Asset Management transactions*](#)
- [*Asset records—Require Account option*](#)
- [*Reprinting the FA Posting to General Ledger report*](#)
- [*Rebuilding integrated batches*](#)

Migrating from another fixed assets system

After converting from another system—but before completely implementing Fixed Asset Management—we recommend that you mark the transactions already in General Ledger as posted. Use the Fixed Assets General Ledger Posting window to mark the transactions as posted.

To migrate from another fixed assets system:

1. Open the Fixed Assets General Ledger Posting window.
(Microsoft Dynamics GP menu >> Tools >> Routines >> Fixed Assets >> GL Posting)



2. Enter zeros in the Beginning Period field and enter the period you are balancing through in the Ending Period field in the format YYYY-PPP, where Y is the year and P is the period.
3. Enter a transaction date.
4. You can enter a comment to be displayed in the General Ledger Batch Transmittal and Transaction Entry windows.

- Choose Continue. The batch number assigned to this batch will be displayed and the FA Posting to General Ledger report will be printed when the process is complete.
- If you've already posted these amounts in your previous fixed assets system, delete this batch from General Ledger. This will ensure that the data from that system will be identified as posted in Fixed Asset Management. For more information, refer to the General Ledger documentation.


As you finish transferring your data to Fixed Asset Management, you can continue to enter zeros in the Beginning Period field and the current period in the Ending Period field. Using this set of dates, all current period activity—along with any prior period adjustments—will be included without doubling posted entries.

Updating General Ledger with Fixed Asset Management transactions

Use the Fixed Assets General Ledger Posting window to update General Ledger with Fixed Asset Management transactions.

To update General Ledger with Fixed Asset Management transactions:

- Open the Fixed Assets General Ledger Posting window.
(Microsoft Dynamics GP menu >> Tools >> Routines >> Fixed Assets >> GL Posting)



- Enter a range of periods in the Beginning Period and Ending Period fields.



We recommend that you enter zeros for the beginning period to include any prior period adjustments that have been made since the last time transactions were posted to General Ledger.

- Enter the transaction date. This date will be displayed as the transaction date in the General Ledger journal voucher and will be used by General Ledger to determine the fiscal period these entries will be posted to.
- Select the book IDs to post the transactions assigned to the selected books to General Ledger. All book IDs for which you have marked the Post to General Ledger in the Book Setup window (Microsoft Dynamics GP menu >> Tools >> Setup >> Fixed Assets >> Book) are available for selection.



The reporting ledger assigned to the book ID will be applied when you post fixed assets transactions in General Ledger.

5. You can enter a comment to be displayed in the General Ledger Batch Transmittal and Transaction Entry windows.



The selected book ID will be appended to the comment field and updated in the Distribution Reference field for the General Ledger transaction in the Transaction Entry window (Transactions >> Financial >> General).

6. Choose Continue. The batch number assigned to this batch will be displayed and the FA Posting to General Ledger report will be printed when the process is complete. You also can reprint this report.
7. You can edit or post this batch in General Ledger.

Asset records—Require Account option

Before you create asset records or perform any maintenance on asset records, you must mark Require Account in the Fixed Assets Company Setup window to ensure that all Fixed Asset Management transactions that are saved and added to the Financial Detail table have a valid account number. You also must create an asset account record before any book record can be saved for that asset.

For more information, refer to [Purchasing integration options](#) on page 24 and [Modifying an asset account record](#) on page 42.

Reprinting the FA Posting to General Ledger report

Use the Fixed Assets General Ledger Posting window to reprint the FA Posting to General Ledger report. If you need to rebuild integrated batches, refer to [Rebuilding integrated batches](#) on page 109.

To reprint the FA Posting to General Ledger report:

1. Open the Fixed Assets General Ledger Posting window.
(Microsoft Dynamics GP menu >> Tools >> Routines >> Fixed Assets >> GL Posting)
2. Choose Reprint and enter or select the batch to reprint.
3. Close the window.

Rebuilding integrated batches

Before you can reprint the FA Posting to General Ledger report, you might have to rebuild the integrated batches. If there are no batch IDs displayed in the Batch Lookup window, use the Fixed Assets Reconcile window to rebuild integrated batches.

To reprint the FA Posting to General Ledger report, refer to [Reprinting the FA Posting to General Ledger report](#) on page 109.

To rebuild integrated batches:

1. Open the Fixed Assets Reconcile window.
(Microsoft Dynamics GP menu >> Tools >> Utilities >> Fixed Assets >> Reconcile)



2. Mark Create Batch Headers and choose Reconcile.
3. After the FA Create Batch Headers report is printed, close the window.

Chapter 15: Physical inventory

You can reconcile the actual physical location for an asset to the physical location ID entered for the asset. You might determine the actual physical location by using a bar-coding system. You also can identify missing or misplaced assets by using the physical inventory reconciliation process.

To verify recorded assets actually exist, and are recorded in the correct physical location, you should reconcile physical inventory.

The following information is discussed:

- [Importing physical location IDs for existing assets](#)
- [Creating an asset labels file](#)
- [Reconciling physical locations for assets](#)

Importing physical location IDs for existing assets

Before you reconcile physical locations, asset records must have a physical location ID and label. Use the Asset Import/Export window to import asset label and physical location ID values from an external source, such as a bar coding system.

The information to be imported must be in a comma- or tab-delimited format and should contain the following fields:

Field	Additional information
Asset ID	Required field
Asset Suffix	Required field
Asset Label	To enter a new value, enter up to 19 alphanumeric characters. To keep the current value in the asset general information record unchanged, leave this field blank.
Physical Location ID	To enter a new value, enter up to 15 alphanumeric characters. To keep the current value in the asset general information record unchanged, leave this field blank.

To import physical location IDs for existing assets:

1. Open the Asset Import/Export window.
(Microsoft Dynamics GP menu >> Tools >> Utilities >> Fixed Assets >> Asset Import/Export)
2. Mark Export and select Asset ID & Suffix.
3. Enter or find the name and location of the file to export the data to and select a character delimiter—comma or text.
4. Choose Continue. The file that is created will contain the asset ID and suffix of every active asset that is set up in Fixed Asset Management.
5. Using Microsoft Excel or Word, open the file containing the data you just exported. You can add the asset label and physical location ID information to the asset ID and suffix information to this file.
6. In the Asset Import/Export window, mark Import and select Physical Inventory Info.

7. Enter or find the location and name of the file to import and select a character delimiter.
8. Choose Continue to import the physical location information. The FA Physical Inventory Information Import report will be printed.

Creating an asset labels file

Use the Asset Import/Export window to create a file with asset labels. These labels can be printed in some form and attached to each asset as an identifier. There is not a standard asset label report.

To create an asset labels file:

1. Open the Asset Import/Export window.
(Microsoft Dynamics GP menu >> Tools >> Utilities >> Fixed Assets >> Asset Import/Export)
2. Mark Export and select Asset Label.
3. Enter or find the name and location of the file to export the data to and select a character delimiter—comma or text.
4. Choose Continue to print asset labels to a file.

Reconciling physical locations for assets

You can import information from another source, such as a bar-code reader, into Fixed Asset Management. The information must be in a comma- or tab-delimited format and should contain the following information:

Field name	Field type
Physical Location ID	15 string
Asset Label	19 string
Verified Date	MMDDYY,MM/DD/YY, MMDDCCYY, OR MM/DD/CCYY
PIN*	15 string
*The PIN is a personal identifier of the person(s) doing the physical inventory.	

If the item data has been imported previously, but not reconciled yet, a message will appear and you can choose one of the following options:

- Delete all
- Replace duplicates
- Add new items only

Discrepancies in the Fixed Assets Inventory file can be corrected using the Physical Inventory window. Discrepancies in the recorded value can be corrected on the asset card, or automatically—if the discrepancies are large—by creating an asset group, then entering a mass-change transaction to correct all the discrepancies at once.

Use the Missing Physical Inventory and Misplaced Physical Inventory windows to view assets that are considered missing or misplaced in Fixed Asset Management.


Missing Indicates assets with a recorded asset label were not found in the physical inventory.

Misplaced Indicates one of the following situations has occurred:

- The physical location in the fixed assets system is different from the inventoried asset, including no recorded physical location.
- The inventoried asset is not recorded in the fixed assets system.
- The inventoried asset is not active—it is retired or partially open.

To reconcile physical locations for assets:

1. Open the Physical Inventory window.
(Microsoft Dynamics GP menu >> Tools >> Routines >> Fixed Assets >> Physical Inventory)



2. Select All Locations or enter or select a specific physical location ID.
3. Enter the physical inventory information—asset label, PIN, and verified date—manually or choose Import to update the Fixed Assets Inventory File.
4. Choose Missing to open the Missing Physical Inventory window. Choose Misplaced to open the Misplaced Physical Inventory window.
5. Choose Create Group to open the Create Group window and enter a new group name.
6. Choose Create to add the missing or misplaced assets to the new group.
7. Choose OK to close the Missing Physical Inventory window or the Misplaced Physical Inventory window.
8. Choose Update to update inventory information in the asset general information record and Physical Location ID Setup record.

The Verified Date and PIN will be saved to each reconciled general information record for each reconciled asset. Only items that haven't been reconciled will remain in the imported file after the update is complete.

9. Close the Physical Inventory window.

Part 5: Utilities and detail file activity

This part of the documentation provides information about maintaining the integrity of your Fixed Asset Management data by reconciling your records and maintaining the Fixed Asset Management data tables.

This part includes the following information:

- [Chapter 16, “Table maintenance.”](#) explains how to minimize the risk of damage to your data and to quickly recover your data from damage if it occurs.
- [Chapter 17, “Financial detail file activity.”](#) provides the financial information relating to Fixed Asset Management activities.

Chapter 16: Table maintenance

You should reconcile asset records if you discover inconsistencies in reports or if a system problem occurs and you need to verify that your Fixed Asset Management data is accurate.

You can delete asset records entered incorrectly or remove detail for an asset. You also can delete specific detail for items that have an unapplied amount equal to zero.



Be sure to back up your data before completing any of these procedures.

The following information is discussed:

- [Reconciling asset information](#)
- [Deleting an asset](#)
- [Deleting fixed assets purchasing transactions](#)

Reconciling asset information

Use the Fixed Assets Reconcile window to reconcile asset information and book ITC records. You can insert account numbers in any account that was left blank at the asset level and update any blank account with the corresponding default accounts entered in the Fixed Assets Company Setup window. You also can verify that each book ITC record has a Net Cost Basis equal to the Cost Basis in the asset book record.

You can update or verify your asset data using one of the following reconciliation processes:

Asset accounts Verifies that there are no blank account numbers in any asset account records. If there are blank accounts, default accounts selected in the Fixed Assets Company Setup window will be saved to the asset account record.

Asset labels Updates blank asset label fields. If a blank asset label field exists in a asset general information record, the asset ID and suffix will be saved to the Asset Label field.

Book ITC Forces the net cost basis in the Book/ITC record to be in balance with the cost basis in the Asset Book record. Only asset books that have a Book/ITC record will be reconciled.

Create batch headers Creates a list of fixed assets general ledger batch numbers (FATRX) to use for reprinting the FA Posting to General Ledger report.

Custodians Creates a list of assets with a custodian in the Asset General Information record, but the custodian is not also in the employee record.



Be sure to back up your data before completing any of these procedures.

To reconcile asset information:

1. Open the Fixed Assets Reconcile window.
(Microsoft Dynamics GP menu >> Tools >> Utilities >> Fixed Assets >> Reconcile)
2. Mark Asset Accounts to update asset account information.
3. Mark Asset Labels to update blank asset label fields.
4. Mark Book ITC to update asset book cost basis information.
5. Mark Create Batch Header to create a list of fixed assets general ledger batch numbers.
6. Mark Custodians to create a list of assets without a custodian in the employee record.
7. Choose Reconcile and then choose OK. You can print a report for each process to view the asset records that were updated.

Deleting an asset

Use the Asset Delete Utility window to delete an asset record and all associated records. You should delete an asset only when the asset has been entered incorrectly.




Use this utility with caution. Your books could become out of balance if the asset book dollar amounts that are already posted in General Ledger are deleted from the Fixed Assets Financial Detail File.

There is no audit trail for the deleted asset, although the Asset Delete Report will be printed.

If you've already used the General Ledger integration process to post dollar amounts for an asset, you must make manual General Ledger entries to reverse the cost and year-to-date depreciation for the asset you're deleting.

To delete an asset:

1. Open the Asset Delete Utility window.
(Microsoft Dynamics GP menu >> Tools >> Utilities >> Fixed Assets >> Delete)



2. Enter an asset ID to delete.
3. Choose Delete to delete the asset and print the Fixed Asset Delete report. You can refer to this report when making manual adjustments to the General Ledger.


Deleting fixed assets purchasing transactions

Use the FA Purchasing Trxs Purge window to delete transactions that asset records have been created from. You also can remove specific information for each asset in the Fixed Assets Purchasing Transactions window using this window.

You also can use the FA Purchasing Trxs Purge window to delete transactions that have an unapplied amount equal to zero. If an unapplied amount is not equal to zero, the transaction will not be deleted.

To delete fixed assets purchasing transactions:

1. Open the FA Purchasing Trxs Purge window.
(Microsoft Dynamics GP menu >> Tools >> Utilities >> Fixed Assets >> Purge Purchasing Transactions)



2. Enter or select control numbers to specify the range of data to delete.
3. Choose OK.

Chapter 17: Financial detail file activity

The Financial Detail File contains financial information relating to the many Fixed Asset Management activities. For example, records are added to this file when you add, depreciate, retire, or transfer an asset. When you change fields related to depreciation calculations, records also are written to this file. The following is a table reference to the Financial Detail File and is organized by type of activity.

The following information is discussed:

- [*Activity table abbreviations and descriptions*](#)
- [*Activity table for adding a record*](#)
- [*Activity table for changing a record*](#)
- [*Activity table for mass changes to records*](#)
- [*Activity table for deleting a record*](#)
- [*Activity table for depreciating a record*](#)
- [*Activity detail for transferring a record*](#)
- [*Activity table for mass transfer of records*](#)
- [*Activity table for retiring a record*](#)
- [*Activity detail for mass retiring records*](#)
- [*Activity detail for unretiring records*](#)

Activity table abbreviations and descriptions

You can use the Financial Detail Inquiry window to view most of the information contained in the following activity tables. Use the following table to view descriptions of abbreviations in the activity tables.

Abbreviation	Description
(+)	Debit
(-)	Credit
BO	Backout Date
DTD	Depreciated To Date
FDCY	First Day of Currency Year
FDPY	First Day of Prior Year
FPCY	First Period of Current Year
LDPY	Last Day of Prior Year
LPPY	Last Period of Prior Year
PIS	Place in Service Date
PRD	Prorated Retire Date
ORIG	Same as in Original Record
PDTD	Period Depreciated To Date
TD	Transfer Date

Activity table for adding a record

When you add an asset record to Fixed Asset Management, specific accounts are debited and credited. Refer to the following table for the effect on the asset accounts.

Account	Effect on account	Fiscal year affected	Source doc	Fiscal period	Depreciated from date	Depreciated to date
Cost	(+)	Current	FAADD	DTD	PIS	DTD
Clearing	(-)	Current	FAADD	DTD	PIS	DTD
If life-to-date depreciation is entered (for portion pertaining to prior years)						
Prior Year Depreciation	(+)	Current	FAADD	earlier of DTD or LPPY	PIS	earlier of DTD or LPPY
Depreciation Reserve	(-)	Current	FAADD	earlier of DTD or LPPY	PIS	earlier of DTD or LPPY
If year-to-date depreciation is entered						
Depreciation Expense	(+)	Current	FAADD	DTD	FDCY (Book Setup window)	DTD
Depreciation Reserve	(-)	Current	FAADD	DTD	FDCY (Book Setup window)	DTD

Activity table for changing a record

When you change information in an asset record, specific accounts are debited and credited. Refer to the following table for the effect on the asset accounts.

Account	Effect on account	Fiscal year affected	Source doc	Fiscal period	Depreciated from date	Depreciated through date
If cost is increased						
Cost	(+)	Current	FACHG	DTD	PIS	DTD
Clearing	(-)	Current	FACHG	DTD	PIS	DTD
If cost is decreased						
Cost	(-)	Current	FACHG	DTD	PIS	DTD
Clearing	(+)	Current	FACHG	DTD	PIS	DTD
If life-to-date depreciation is increased without changing year-to-date depreciation						
Prior Year Depreciation	(+)	Current	FACHG	LPPY	PIS	LDPY
Depreciation Reserve	(-)	Current	FACHG	LPPY	PIS	LDPY
If life-to-date depreciation is decreased without changing year-to-date depreciation						
Prior Year Depreciation	(-)	Current	FACHG	LPPY	PIS	LDPY
Depreciation Reserve	(+)	Current	FACHG	LPPY	PIS	LDPY
If year-to-date depreciation is increased and life-to-date depreciation is increased by the same amount						
Depreciation Expense	(+)	Current	FACHG	DTD	FDCY	DTD
Depreciation Reserve	(-)	Current	FACHG	DTD	FDCY	DTD
If year-to-date depreciation is increased and life-to-date depreciation is increased by a smaller amount						
Depreciation Expense	(+)	Current	FACHG	DTD	FDCY	DTD
Depreciation Reserve	(-)	Current	FACHG	DTD	FDCY	DTD

Account	Effect on account	Fiscal year affected	Source doc	Fiscal period	Depreciated from date	Depreciated through date
Depreciation Reserve	(+)	Current	FACHG	LPPY	PIS	LDPY
Prior Year Expense	(-)	Current	FACHG	LPPY	PIS	LDPY
If year-to-date depreciation is increased and life-to-date depreciation is increased by a greater amount						
Depreciation Expense	(+)	Current	FACHG	DTD	FDCY	DTD
Depreciation Reserve	(-)	Current	FACHG	DTD	FDCY	DTD
Prior Year Expense	(+)	Current	FACHG	LPPY	FDCY	LDPY
Depreciation Reserve	(-)	Current	FACHG	LPPY	PIS	LDPY
If year-to-date depreciation is increased and life-to-date depreciation is decreased or not changed						
Depreciation Expense	(+)	Current	FACHG	DTD	FDCY	DTD
Depreciation Reserve	(-)	Current	FACHG	DTD	FDCY	DTD
Depreciation Reserve	(+)	Current	FACHG	LPPY	PIS	LDPY
Prior Year Expense	(-)	Current	FACHG	LPPY	PIS	LDPY
If year-to-date depreciation is increased and life-to-date depreciation is decreased by the same amount						
Depreciation Reserve	(+)	Current	FACHG	DTD	FDCY	DTD
Depreciation Expense	(-)	Current	FACHG	DTD	FDCY	DTD
If year-to-date depreciation is decreased and life-to-date depreciation is decreased by a smaller amount						
Depreciation Reserve	(+)	Current	FACHG	DTD	FDCY	DTD
Depreciation Expense	(-)	Current	FACHG	DTD	FDCY	DTD
Prior Year Expense	(+)	Current	FACHG	LPPY	PIS	LDPY
Depreciation Expense	(-)	Current	FACHG	LPPY	PIS	LDPY
If year-to-date depreciation is decreased and life-to-date depreciation is decreased by a greater amount						
Depreciation Reserve	(+)	Current	FACHG	DTD	FDCY	DTD
Depreciation Expense	(-)	Current	FACHG	DTD	FDCY	DTD
Depreciation Expense	(+)	Current	FACHG	LPPY	PIS	LDPY
Prior Year Expense	(-)	Current	FACHG	LPPY	PIS	LDPY
If year-to-date depreciation is decreased and life-to-date depreciation is increased or does not change						
Depreciation Reserve	(+)	Current	FACHG	DTD	FDCY	DTD
Depreciation Expense	(-)	Current	FACHG	DTD	FDCY	DTD
Prior Year Expense	(+)	Current	FACHG	LPPY	PIS	LDPY

Account	Effect on account	Fiscal year affected	Source doc	Fiscal period	Depreciated from date	Depreciated through date
Depreciation Expense	(-)	Current	FACHG	LPPY	PIS	LDPY
Reset Year (Backout)						
Depreciation Expense	(-)	Current	FACHG-R	ORIG	ORIG or BO+1	ORIG
Depreciation Reserve	(+)	Current	FACHG-R	ORIG	ORIG or BO+1	ORIG
Reset Year (Re-depreciate) When reset life is processed, the two reset year options are processed after the reset life options.						
Depreciation Expense	(+)	Current	FACHG-R	PDTD	OLD PDTD+1	PDTD
Depreciation Reserve	(-)	Current	FACHG-R	PDTD	OLD PDTD+1	PDTD
Reset Life (Backout)						
Prior Year Depreciation	(-)	Current	FACHG-R	LPPY	PIS	LDPY
Depreciation Reserve	(+)	Current	FACHG-R	LPPY	PIS	LDPY
Reset Life (Re-depreciate)						
Prior Year Depreciation	(+)	Current	FACHG-R	PDTD	OLD PDTD+1	PDTD
Depreciation Reserve	(-)	Current	FACHG-R	PDTD	OLD PDTD+1	PDTD

Activity table for mass changes to records

When you change a group of asset records, specific accounts are debited and credited. Refer to the following table for the effect on the asset accounts.

Account	Effect on account	Fiscal year affected	Source doc	Fiscal period	Depreciated from date	Depreciated to date
Reset Year (Backout)						
Depreciation Expense	(-)	Current	FAMCH-R	ORIG	ORIG or BO+1	ORIG
Depreciation Reserve	(+)	Current	FAMCH-R	ORIG	ORIG or BO+1	ORIG
Reset Year (Re-Depreciate)						
Depreciation Expense	(+)	Current	FAMCH-R	PDTD	OLD PDTD+1	PDTD
Depreciation Reserve	(-)	Current	FAMCH-R	PDTD	OLD PDTD+1	PDTD
Reset Life (Backout)						
Prior Year Depreciation	(-)	Current	FAMCH-R	LPPY	PIS	LDPY
Depreciation Reserve	(+)	Current	FAMCH-R	LPPY	PIS	LDPY
Reset Life (Re-Depreciate) When reset life is processed, the two reset year options are processed after the reset life options						
Prior Year Depreciation	(+)	Current	FAMCH-R	PDTD	OLD PDTD+1	PDTD
Depreciation Reserve	(-)	Current	FAMCH-R	PDTD	OLD PDTD+1	PDTD

Activity table for deleting a record

When you delete an asset record, financial records won't be created. You must debit and credit specific General Ledger accounts. Refer to the following table for the effect on the asset accounts.

Account	Effect on account	Fiscal year affected	Source doc	Fiscal period	Depreciated from date	Depreciated to date
Cost	(-)	Current	FADLT	DTD	PIS	DTD
Clearing	(+)	Current	FADLT	DTD	PIS	DTD
Depreciation Expense	(-)	Current	FADLT	ORIG	ORIG	ORIG
Depreciation Reserve	(+)	Current	FADLT	ORIG	ORIG	ORIG

Activity table for depreciating a record

When you process depreciation for an asset record, specific accounts are debited and credited. Refer to the following table for the effect on the asset accounts.

Account	Effect on account	Fiscal year affected	Source doc	Fiscal period	Depreciated from date	Depreciated to date
Depreciation Expense	(+)	Current	FADEP	PDTD	OLD PDTD+1	PDTD
Depreciation Reserve	(-)	Current	FADEP	PDTD	OLD PDTD+1	PDTD
Depreciate one asset (if a target date is entered that is earlier than the depreciated to date)						
Depreciation Expense	(-)	Current	FADEP-O	ORIG	ORIG or BO+1	ORIG
Depreciation Reserve	(+)	Current	FADEP-O	ORIG	ORIG or BO+1	ORIG
Depreciate one asset (if a target date is entered that is later than the depreciated to date)						
Depreciation Expense	(+)	Current	FADEP-O	PDTD	OLD PDTD+1	PDTD
Depreciation Reserve	(-)	Current	FADEP-O	PDTD	OLD PDTD+1	PDTD
Reset Year (Backout)						
Depreciation Expense	(-)	Current	FADEP-R	ORIG	ORIG or BO+1	ORIG
Depreciation Reserve	(+)	Current	FADEP-R	ORIG	ORIG or BO+1	ORIG
Reset Year (Re-Depreciate)						
Depreciation Expense	(+)	Current	FADEP-R	PDTD	OLD PDTD+1	PDTD
Depreciation Reserve	(-)	Current	FADEP-R	PDTD	OLD PDTD+1	PDTD
Reset Life (Backout)						
Prior Year Depreciation	(-)	Current	FADEP-R	LPPY	PIS	LDPY
Depreciation Reserve	(+)	Current	FADEP-R	LPPY	PIS	LDPY
Reset Life (Re-Depreciate) When reset life is processed, the two reset year options are processed after the reset life options						
Prior Year Depreciation	(+)	Current	FADEP-R	PDTD	OLD PDTD+1	PDTD

Account	Effect on account	Fiscal year affected	Source doc	Fiscal period	Depreciated from date	Depreciated to date
Depreciation Reserve	(-)	Current	FADEP-R	PDTD	OLD PDTD+1	PDTD

Activity detail for transferring a record

When you transfer an asset record, specific accounts are debited and credited. Refer to the following table for the effect on the asset accounts.

Account	Effect on account	Fiscal year affected	Source doc	Fiscal period	Depreciated from date	Depreciated to date
If transfer is later than the depreciated to date						
Depreciation Expense	(+)	Current	FAXFR	PDTD	OLD PDTD+1	PDTD
Depreciation Reserve	(-)	Current	FAXFR	PDTD	OLD PDTD+1	PDTD
If transfer is earlier than the depreciated to date						
Depreciation Expense	(-)	Current	FAXFR	ORIG	ORIG or BO+1	ORIG
Depreciation Reserve	(+)	Current	FAXFR	ORIG	ORIG or BO+1	ORIG
Partial Transfer (transferring partial to new asset records) Creating "TO" asset						
Cost	(+)	Current	FAXFR-P	DTD	PIS	DTD
Clearing	(-)	Current	FAXFR-P	DTD	PIS	DTD
Depreciation Expense	(+)	Current	FAXFR-P	DTD	PIS or FDCY	DTD
Depreciation Reserve	(-)	Current	FAXFR-P	DTD	PIS or FDCY	DTD
Prior Year Depreciation	(+)	Current	FAXFR-P	LPPY	PIS	LDPY
Depreciation Reserve	(-)	Current	FAXFR-P	LPPY	PIS	LDPY
Partial Transfer (transferring partial to new asset records) Reducing "FROM" asset						
Cost	(-)	Current	FAXFR-P	DTD	PIS	DTD
Clearing	(+)	Current	FAXFR-P	DTD	PIS	DTD
Depreciation Expense	(-)	Current	FAXFR-P	DTD	PIS or FDCY	DTD
Depreciation Reserve	(+)	Current	FAXFR-P	DTD	PIS or FDCY	DTD
Prior Year Depreciation	(-)	Current	FAXFR-P	LPPY	PIS	LDPY
Depreciation Reserve	(+)	Current	FAXFR-P	LPPY	PIS	LDPY
Cost/Reserve (transferring cost/reserve to new accounts)						
Cost (To asset account)	(+)	Current	FAXFR-C	TD	PIS	TD
Cost (From asset account)	(-)	Current	FAXFR-C	TD	PIS	TD
Depreciation Reserve (From asset account)	(+)	Current	FAXFR-C	TD	PIS	TD

Account	Effect on account	Fiscal year affected	Source doc	Fiscal period	Depreciated from date	Depreciated to date
Depreciation Reserve (To asset account)	(-)	Current	FAXFR-C	TD	PIS	TD

Activity table for mass transfer of records

When you transfer a group of asset records, specific accounts are debited and credited. Refer to the following table for the effect on the asset accounts.

Account	Effect on account	Fiscal year affected	Source doc	Fiscal period	Depreciated from date	Depreciated to date
If transfer is later than the depreciated to date						
Depreciation Expense	(+)	Current	FAMXF	PDTD	OLD PDTD+1	PDTD
Depreciation Reserve	(-)	Current	FAMXF	PDTD	OLD PDTD+1	PDTD
If transfer is earlier than the depreciated to date						
Depreciation Expense	(-)	Current	FAMXF	ORIG	ORIG or BO+1	ORIG
Depreciation Reserve	(+)	Current	FAMXF	ORIG	ORIG or BO+1	ORIG
Cost/Reserve (transferring cost/reserve to new accounts)						
Cost (To asset account)	(+)	Current	FAMXF-C	TD	PIS	TD
Cost (From asset account)	(-)	Current	FAMXF-C	TD	PIS	TD
Depreciation Reserve (From asset account)	(+)	Current	FAMXF-C	TD	PIS	TD
Depreciation Reserve (To asset account)	(-)	Current	FAMXF-C	TD	PIS	TD

Activity table for retiring a record

When you retire an asset, specific accounts are debited and credited. Refer to the following table for the effect on the asset accounts.

Account	Effect on account	Fiscal year affected	Source doc	Fiscal period	Depreciated from date	Depreciated through date
PARTIAL RETIREMENT						
Creating new records to be retired						
Cost	(+)	Current	FARET-P	DTD	PIS	DTD
Clearing	(-)	Current	FARET-P	DTD	PIS	DTD
Depreciation Expense	(+)	Current	FARET-P	DTD	PIS or FDCY	DTD
Depreciation Reserve	(-)	Current	FARET-P	DTD	PIS or FDCY	DTD
Prior Year Depreciation	(+)	Current	FARET-P	LPPY	PIS	DPY
Depreciation Reserve	(-)	Current	FARET-P	LPPY	PIS	LDPY

PART 5 UTILITIES AND DETAIL FILE ACTIVITY

Account	Effect on account	Fiscal year affected	Source doc	Fiscal period	Depreciated from date	Depreciated through date
Reducing original asset						
Cost	(-)	Current	FARET-P	DTD	DTD	DTD
Clearing	(+)	Current	FARET-P	DTD	DTD	DTD
Depreciation Expense	(-)	Current	FARET-P	DTD	PIS or FDCY	DTD
Depreciation Reserve	(+)	Current	FARET-P	DTD	PIS or FDCY	DTD
Prior Year Depreciation	(-)	Current	FARET-P	LPPY	PIS	LDPY
Depreciation Reserve	(+)	Current	FARET-P	LPPY	PIS	LDPY
FULL OR PARTIAL RETIREMENT						
If prorated retire date is later than the depreciated to date						
Depreciation Expense	(+)	Current	FARET	PDTD	OLD PDTD+1	PDTD
Depreciation Reserve	(-)	Current	FARET	PDTD	OLD PDTD+1	PDTD
If prorated retired date is earlier than the depreciated to date						
Depreciation Expense	(-)	Current	FARET	ORIG	ORIG or BO+1	ORIG
Depreciation Reserve	(+)	Current	FARET	ORIG	ORIG or BO+1	ORIG
Prior Year Depreciation (if Retire Date is a prior year)	(-)	Current	FARET	PRD	PRD+1	LDPY
Cost, Accumulated Depreciation, Proceeds, Gain/Loss						
Cost	(-)	Current	FARET	PRD	PIS	PRD
Depreciation Reserve	(+)	Current	FARET	PRD	PIS	PRD
Non-Recognized Gain	(-) Gain					
	(+) Loss	Current	FARET	PRD	PIS	PRD
Recognized Gain	(-) Gain					
	(+) Loss	Current	FARET	PRD	PIS	PRD
Proceeds (Cash Proceeds + Non-Cash Proceeds - Expenses of Sale)	(+)	Current	FARET	PRD	PIS	PRD

Activity detail for mass retiring records

When you retire a group of asset records, specific accounts are debited and credited. Refer to the following table for the effect on the asset accounts.

Account	Effect on account	Fiscal year affected	Source doc	Fiscal period	Depreciated from date	Depreciated through date
If prorated retire date is later than the depreciated to date						
Depreciation Expense	(+)	Current	FAMRT	PDTD	OLD PDTD+1	PDTD
Depreciation Reserve	(-)	Current	FAMRT	PDTD	OLD PDTD+1	PDTD
If prorated retire date is earlier than the depreciated to date						

Account	Effect on account	Fiscal year affected	Source doc	Fiscal period	Depreciated from date	Depreciated through date
Depreciation Expense	(-)	Current	FAMRT	ORIG	ORIG or BO+1	ORIG
Depreciation Reserve	(+)	Current	FAMRT	ORIG	ORIG or BO+1	ORIG
Prior Year Depreciation (If Retire Date is in a prior year)	(-)	Current	FAMRT	PRD	PRD+1	LDPV
Cost, Accumulated Depreciation, Proceeds, Gain/Loss						
Cost	(-)	Current	FAMRT	PRD	PIS	PRD
Depreciation Reserve	(+)	Current	FAMRT	PRD	PIS	PRD
Non-Recognized Gain	(-) Gain					
	(+) Loss	Current	FAMRT	PRD	PIS	PRD
Recognized Gain	(-) Gain					
	(+) Loss	Current	FAMRT	PRD	PIS	PRD

Activity detail for unretiring records

When you undo an asset retirement, specific accounts are debited and credited. Refer to the following table for the effect on the asset accounts.

Account	Effect on account	Fiscal year affected	Source doc	Fiscal period	Depreciated from date	Depreciated through date
Partial Retirement Undo						
Offsetting the effect of the new retired record that has been created						
Cost	(-)	Current	FARET-PU	DTD	PIS	DTD
Clearing	(+)	Current	FARET-PU	DTD	PIS	DTD
Depreciation Expense	(-)	Current	FARET-PU	DTD	PIS or FDCY	DTD
Depreciation Reserve	(+)	Current	FARET-PU	DTD	PIS or FDCY	DTD
Prior Year Depreciation	(-)	Current	FARET-PU	LPPY	PIS	LDPY
Depreciation Reserve	(+)	Current	FARET-PU	LPPY	PIS	LDPY
Adding back to original asset						
Cost	(+)	Current	FARET-PU	DTD	PIS	DTD
Clearing	(-)	Current	FARET-PU	DTD	PIS	DTD
Depreciation Expense	(+)	Current	FARET-PU	DTD	PIS or FDCY	DTD
Depreciation Reserve	(-)	Current	FARET-PU	DTD	PIS or FDCY	DTD
Prior Year Depreciation	(+)	Current	FARET-PU	LPPY	PIS	LPPY
Depreciation Reserve	(-)	Current	FARET-PU	LPPY	PIS	LPPY
Full or Partial Retirement						

PART 5 UTILITIES AND DETAIL FILE ACTIVITY

Account	Effect on account	Fiscal year affected	Source doc	Fiscal period	Depreciated from date	Depreciated through date
If prorated retire date was later than the depreciated to date						
Depreciation Expense	(-)	Current	FARET-U	ORIG	ORIG	ORIG
Depreciation Reserve	(+)	Current	FARET-U	ORIG	ORIG	ORIG
If prorated retire date was earlier than the depreciated to date						
Depreciation Expense	(+)	Current	FARET-U	ORIG	ORIG	ORIG
Depreciation Reserve	(-)	Current	FARET-U	ORIG	ORIG	ORIG
Prior Year Depreciation (If Retire Date was in a prior year)	(+)	Current	FARET-U	ORIG	ORIG	ORIG
Cost, Accumulated Depreciation, Proceeds, Gain/Loss						
Cost	(+)	Current	FARET-U	ORIG	ORIG	ORIG
Depreciation Reserve	(-)	Current	FARET-U	ORIG	ORIG	ORIG
Non-Recognized Gain	(+) Gain					
	(-) Loss	Current	FARET-U	ORIG	ORIG	ORIG
Recognized Gain	(+) Gain					
	(-) Loss	Current	FARET-U	ORIG	ORIG	ORIG
Proceeds (Cash Proceeds + Non-Cash Proceeds - Expenses of Sale)	(-)	Current	FARET-U	ORIG	ORIG	ORIG

Part 6: Inquiries and reports

This part of the documentation provides information about viewing and printing Fixed Asset Management data and analyzing asset activity by printing specific reports.

This part includes the following information:

- [Chapter 18, "Inquiries,"](#) explains how to view asset information, including financial information.
- [Chapter 19, "Reports,"](#) explains how to create report options and print Fixed Asset Management reports to display specific data.

Chapter 18: Inquiries

You can use the Fixed Asset Management inquiry windows to review asset information and financial information for an asset. You also can view additional information from the Asset Book Inquiry, Book Compare Inquiry, and Financial Detail Inquiry windows by clicking links to open other windows.

You can print inquiry reports by choosing File >> Print in each inquiry window, or by choosing the printer icon button.

The following information is discussed:

- [Viewing asset information](#)
- [Viewing asset book information](#)
- [Comparing asset books](#)
- [Viewing financial detail information](#)
- [Viewing asset retirement information](#)
- [Viewing the error log](#)
- [Viewing transfer information](#)
- [Viewing projected depreciation information](#)
- [Viewing purchasing transactions information](#)
- [General Ledger inquiries](#)

Viewing asset information

Use the Asset Inquiry and Asset General Inquiry windows to view specific information about an asset that does not directly relate to depreciation, such as the asset description, class ID, quantity, and property type.

From the Asset Inquiry window, use the Go To button to open the following windows:

Go To button option	Window that opens
General	Asset General Inquiry window
Maint/Manuf	Asset Maintenance/Manufacturer Inquiry window
Purchase	Asset Purchase Inquiry window
Account	Asset Account Inquiry window
Insurance	Asset Insurance Inquiry window
Lease	Asset Lease Inquiry window
User Data	Asset User Data Inquiry window

To view asset information:

1. Open the Asset Inquiry window.
(Inquiry >> Fixed Assets >> General)

2. Enter or select an asset ID. Select one of the following options from the Go To button:

Maint/Manuf Opens the Asset Maintenance/Manufacturer Inquiry window, where you can view asset maintenance and manufacturer information that was entered in the Asset General Information window and the Expand Manufacturer Name window.

Purchase Opens the Asset Purchase Inquiry window, where you can view information that was entered in the Asset General Information window, such as vendor ID, and purchase order number. If the acquisition of the asset originated in Payables Management or Purchase Order Processing, additional information might be displayed. Click the Voucher/Receipt Number link to view the originating window.

Account Opens the Asset Account Inquiry window, where you can view the account information that was entered in the Asset Account window.

Insurance Opens the Asset Insurance Inquiry window, where you can view insurance class, replacement cost, and depreciated reproduction cost information that was entered in the Asset Insurance window.

Lease Opens the Asset Lease Inquiry window, where you can view the lease company ID, lease type, and interest rate information that was entered in the Asset Lease window.

User Data Opens the Asset User Data Inquiry window, where you can view user-defined information that was entered in the Asset User Data window.

3. Close the Asset Inquiry window.


Viewing asset book information

Use the Asset Book Inquiry and Asset Book ITC Inquiry windows to view depreciation information and asset values, such as the cost basis of the asset, salvage value, and net book value.


To view detail transactions for a specific value of an asset, you can open the Financial Detail Inquiry window by clicking on the Cost Basis, YTD Depreciation, and YTD Depreciation links.

To view asset book information:

1. Open the Asset Book Inquiry window.
(Inquiry >> Fixed Assets >> Book)



2. Enter or select an asset ID, suffix, and book ID.
3. Choose the ITC/Cost button to open the Asset Book ITC Inquiry window.



4. Choose OK to close the Asset Book ITC Inquiry window.
5. Choose OK to close the Asset Book Inquiry window.

Comparing asset books

Use the Book Compare Inquiry window to compare depreciation characteristics and depreciation balances for up to three books for an asset. This is useful to see the difference in the depreciation values calculated using different rules. You also can open the Asset Book Inquiry and the Financial Detail Inquiry windows from this window.

To compare asset books:

1. Open the Book Compare Inquiry window.
(Inquiry >> Fixed Assets >> Book Compare)

The screenshot shows the 'Book Compare Inquiry' window for asset ID 00003, a Side Chair located in ALPHARETTA. The window compares three books: INTERNAL, AMT, and another AMT. The data is as follows:

	INTERNAL	AMT	AMT
Reporting Ledger	BASE		
Cost Basis	\$650.00	\$650.00	\$650.00
Salvage Value	\$0.00	\$0.00	\$0.00
YTD Depreciation	\$15.48	\$12.39	\$12.39
LTD Depreciation	\$185.72	\$151.33	\$151.33
Net Book Value	\$464.28	\$498.67	\$498.67
Place in Service Date	3/1/2015	3/1/2015	3/1/2015
Depr. Begin Date	2/28/2015	7/2/2015	7/2/2015
Depreciated to Date	2/28/2017	2/28/2017	2/28/2017
Original Life	7 Years 0 Days	10 Years 0 Days	10 Years 0 Days
Remaining Life	5 Years 0 Days	8 Years 124 Days	8 Years 124 Days
Depreciation Method	Straight-Line Ori	150% DB	150% DB
Averaging Convention	Full Period	Half-Year	Half-Year
Switchover	No Switch	Straight-Line	Straight-Line
Luxury Automobile	No	No	No

2. Enter or select an asset ID and suffix.
3. Select up to three books—one book for each column.
4. Choose the Book button for each book to open the Asset Book Inquiry window.
5. Choose the Financial button for each book to open the Financial Detail Inquiry window. For more information, refer to [Viewing financial detail information](#) on page 137.
6. Choose OK in the Book Compare Inquiry window to close the window.

Viewing financial detail information

Use the Financial Detail Inquiry window to view the financial detail records for an asset, such as the fiscal period, batch number, transaction account and date, source document, and amount. These records include information about an asset that has been added, changed, depreciated, retired, or transferred. You can view specific information by selecting options to restrict the information.

To view additional information for each transaction, you can click on the Amount link to open the Financial Detail Display window. You also can open the Financial Detail Inquiry window by clicking the Cost Basis link in the Asset Book Inquiry and Asset Book Compare windows.

To view financial detail information:

1. Open the Financial Detail Inquiry window.
(Inquiry >> Fixed Assets >> Financial Detail)
2. Enter or select an asset ID and suffix and select a book ID.
3. Select a sorting option at the bottom of the window.
4. To restrict the information displayed in this window, select the appropriate sorting option and then select one or more of the following options:


Period filter Displays only records for the specified Fixed Asset Management period. To view all records for a year, enter zeros for the period. This field is in the format YYYY- PPP, where Y is a year and P is a period.

GL Batch # filter Displays only those records that are included in the batch number you enter.

Transaction Account Type filters Displays only records with a certain transaction account type or all transaction account types. If you mark more than one transaction account type filter, assets will be displayed for each type. Mark All Types to include all asset records, regardless of their transaction account type. Choose Redisplay.

Source Doc. filters Displays only records with the source document you select. If you mark more than one source document filter, assets will be displayed for each type. Mark All Documents to include all asset records, regardless of their source document. Choose Redisplay.

5. Select a transaction and click the Amount link to open the Financial Detail Display window.




6. Choose OK to close the Financial Detail Display window.
7. Choose OK in the Financial Detail Inquiry window.

Viewing asset retirement information

Use the Retirement Display window to view the cash proceeds, non-cash proceeds, expenses of sale, and information related to the retirement of an asset.

To view asset retirement information:

1. Open the Retirement Inquiry window.
(Inquiry >> Fixed Assets >> Retirement)
2. Enter or select an asset ID and suffix. If the asset was partially retired, more than one line might be displayed.
3. Select a line and click the Event link to open the Retirement Display window.




4. Choose OK to close the window.

Viewing the error log

Use the Error Log Inquiry window to determine the type of problem that has occurred. When a problem occurs during a process, information is displayed in the Error Log Inquiry window describing the process occurring at the time of the problem and possibly listing the table and record where the problem occurred. View this information before you call technical support.

To view the error log:

1. Open the Error Log Inquiry window:
(Inquiry >> Fixed Assets >> Error Log)



2. Enter the date to view the messages for.
3. Choose Print to print the FA Error Log Listing report.
4. Choose Cancel to close the window.

Viewing transfer information

Use the Transfer Display window to view information about an asset transferred from one asset ID, location ID, physical location ID, master asset ID, structure ID, or account number to another. You also can view the date and time of the transfer and any partial transfer information.

To view transfer information:

1. Open the Transfer Inquiry window.
(Inquiry >> Fixed Assets >> Transfer)
2. Enter or select an asset ID and suffix.

4. Select the range of years—and periods, if applicable.
5. Choose OK to close the window.

Viewing purchasing transactions information

Use the Fixed Assets Purchasing Transactions Inquiry window to view transactions originating in Purchase Order Processing or Payables Management. You can view transaction information such as the purchase order number, document date and number, originating amount, and transaction source. Only transactions that haven't been added as assets or haven't been fully applied as assets will be displayed in this window.

To view the purchasing transactions information:

1. Open the Fixed Assets Purchasing Transactions window.
(Inquiry >> Fixed Assets >> Purchasing Transactions)
2. Select a transaction.
 - Click the Vendor ID link to open the Vendor Inquiry window.
 - Click the Voucher/Receipt No. link to display the original purchasing transaction.
 - Click the Amount link to open the Fixed Assets Purchasing Transaction Display window and view the information that will be used to create an asset record.

3. Choose OK in the Fixed Assets Purchasing Transactions window to close the window.

General Ledger inquiries

By clicking links in specific General Ledger inquiry windows, you can open additional windows and view details of the Fixed Asset Management transactions that were posted to General Ledger. Details include account information, the transaction date, and the amount of the transaction. The following table lists the windows displayed by clicking on the links. To open certain windows, the transaction you select must have originated in Fixed Asset Management; the source document must be FA.

In this window	Click this link	Window displayed
Detail Inquiry window	Journal Entry	Transaction Entry Zoom window
History Detail Inquiry window	Journal Entry	Transaction Entry Zoom window
Transaction Entry Zoom window	Source Document	Fixed Assets - General Ledger Zoom window
Journal Entry Inquiry window	Source Document	Fixed Assets - General Ledger Zoom window
Fixed Assets - General Ledger Zoom window	Asset ID	Asset General Inquiry window
	Amount	Financial Detail Display window

Chapter 19: Reports

You can use Fixed Asset Management reports to analyze asset activity and identify errors in transaction entry. You also can use reports to organize necessary information for financial, tax, and other regulatory reporting requirements.

Use this information to guide you through printing reports and working with report options.

The following information is discussed:

- [Fixed Asset Management reports summary](#)
- [Report destinations and formats](#)
- [Processing reports on a process server](#)
- [Creating report options](#)
- [Printing a report with an option](#)
- [Customizing a report](#)
- [Fixed Asset Management Microsoft SQL® Server Reporting Services reports](#)

Fixed Asset Management reports summary

Some Fixed Asset Management reports are printed automatically when you complete certain procedures. For example, the Asset Delete report is printed when you delete an asset. You can choose to print reports in some windows by choosing File >> Print or the printer icon.

To print some reports, such as analysis or history reports, you must set up report options specifying sorting options and ranges of information to include on the report. For more information, see [Creating report options](#) on page 147.

The following table lists the report types available in Fixed Asset Management and the reports in those categories.

Report type	Reports	Printing methods
Setup	Fixed Assets Account Group Setup Fixed Assets Book Setup Fixed Assets Book Class Setup Fixed Assets Insurance Setup Fixed Assets Class Setup Fixed Assets Company Setup Fixed Assets Lease Company Setup Fixed Assets Physical Location Setup Fixed Assets Purchasing Posting Accounts Setup Fixed Assets Quarter Setup Fixed Assets Retirement Setup Fixed Assets Structure Setup User Fields List Setup	Choose File >> Print in the Setup window or choose the printer icon.
Activity	Annual Activity Annual Activity Cost Basis Report Detail Activity Mid-Quarter Applicability Fixed Assets to General Ledger Reconciliation - Detail Fixed Assets to General Ledger Reconciliation - Summary	Create report options in the Fixed Assets Activity Report options window.

Report type	Reports	Printing methods
Comparison	Book to Book Reconciliation Book to Book YTD Depreciation Comparison	Create report options in the Fixed Assets Comparison Report options window.
Depreciation	Depreciation Detail Depreciation Expense to General Ledger Depreciation Ledger Depreciation Ledger by Class Depreciation Ledger by Class - Summary Depreciation Ledger by Location Depreciation Ledger by Location - Summary Depreciation Ledger by Structure Depreciation Ledger by Structure - Summary	Create report options in the Fixed Assets Depreciation Report options window.
Inventory	Fixed Assets Inventory List Fixed Assets Inventory List by Class Fixed Assets Inventory List by Class -Summary Fixed Assets Inventory List by Location Fixed Assets Inventory List by Location -Summary Fixed Assets Inventory List by Structure Fixed Assets Inventory List by Structure - Summary Locator List Property Ledger Asset List by Master Asset ID	Create report options in the Fixed Assets Inventory Report options window.
Projection	Annual Depreciation Projection - Detail Annual Depreciation Projection - Summary Period Depreciation Projection - Detail Period Depreciation Projection - Summary	Create report options in the Fixed Assets Projection Report options window or choose the printer icon in the Projections Inquiry window.
Transaction	Additions Additions (Multicurrency) Additions by Class Additions by Class - Summary Additions by Class (Multicurrency) Additions by Location Additions by Location - Summary Additions by Location (Multicurrency) Additions by Structure Additions by Structure - Summary Additions by Structure (Multicurrency) Retirements Retirements (Multicurrency) Retirements by Class Retirements by Class (Multicurrency) Retirements by Class - Summary Retirements by Location Retirements by Location - Summary Retirements by Location (Multicurrency) Retirements by Structure Retirements by Structure - Summary Retirements by Structure (Multicurrency) Transfers	Create report options in the Fixed Assets Transaction Report options window.

Report type	Reports	Printing methods
Routines	Financial Detail Summarize Fixed Assets Purge FA Posting to General Ledger FA Posting to General Ledger Reprint Physical Inventory Import Physical Inventory Update Misplaced Physical Inventory Missing Physical Inventory	Choose File >> Print or choose the printer icon in the window you use to complete the procedure or some will be printed automatically when you complete the procedure.
Utilities	ACRS Tables Asset Account Reconciliation Asset Label Reconciliation Asset Delete Report Book ITC Reconciliation Fixed Assets Custodian Reconciliation Create Batch Headers Fixed Assets Migration Results Physical Inventory Info Import Fixed Assets Fiscal Calendar Verify	Choose File >> Print or choose the printer icon button in the window you use to complete the procedure or some will be printed automatically when you complete the procedure.
Miscellaneous Audit Reports	Asset Group Import Fixed Assets Note Update Error Log Listing Fixed Assets Installation Report	Choose File >> Print or choose the printer icon in the window you use to complete the procedure or some will be printed automatically when you complete the procedure.
Inquiry Reports	Asset Inquiry Asset Book Inquiry Report Financial Detail Inquiry Report	Choose File >> Print or choose the printer icon in the window you use to complete the procedure.

If you are using the euro currency reports that include exchange rate information, you can display the dual exchange rates involved in triangulation. When triangulation is used, the Rate Type ID field displays the rate type of the currency relationship that has a variable rate. If both currency relationships have fixed exchanges rates, the Rate Type ID field is blank.

Report destinations and formats

You can print reports to a printer, the screen, a file, or any combination of these destinations.

Printer The report is printed to the default printer set up for your company.

Screen The report appears on the screen and you can then choose to print to the printer. In addition, if you're using an electronic mail system that's compliant with MAPI (Microsoft's Messaging Application Programming Interface), you can e-mail any report that you print to the screen.

File You can select one of the file formats shown in the following table:

File format	Description
Tab-delimited	The tab-separated ASCII character format used by spreadsheet programs, such as Microsoft Excel.
Comma-delimited	The standard comma-separated ASCII character format used by database programs.
Text	Text with no formatting. Use this option only if the application you'll use to read the report can't read any other format.
HTML	A format that can be viewed in a Web browser.
XML Data	A text file that contains an XML representation of the report layout and all the report data. Choose this format if you want to process the report using an external application.
Adobe PDF	This format is available if you have the PDFWriter printer driver installed (included with Acrobat 5 and earlier), or Acrobat Distiller from Acrobat 6 or later. PDF (Portable Document Format) files can be read using Adobe Reader software available from Adobe.
Word Document	The Microsoft Office Open XML (.docx) file format used by Word 2007 or later. You can select this format if you select Template as the report type.

The option to print multicurrency information is available on some report option windows. To print multicurrency versions of your reports, mark the Include Multicurrency Info option.

You can select a printing destination in various ways, depending on which printing method you use.

- If you print a report by choosing File >> Print or the printer icon button while a window is open, the Report Destination window appears, where you can select a destination. (You can select a preferred default destination—Printer or Screen—in the User Preferences window.)
- For activity, comparison, depreciation, inventory, projection, and transaction reports, you select the destination when you create the report options needed to print these reports.

Processing reports on a process server

If you are using the Distributed Process Server (DPS), you can process some reports on your computer or send them to a designated server on the network. Sending long reports to a process server allows you to continue working while the reports are being created.

You can set up the Process Server to process the following Fixed Asset Management activities:

- Depreciation or depreciation projections
- General Ledger posting
- Mass changes
- Mass retirements
- Mass transfers
- Deleting asset data
- Rebuilding tables
- Summarize financial detail
- Year end processes
- Physical inventory update

Creating report options

Report options include specifications of sorting options and range restrictions for a particular report. To print some of the Fixed Asset Management reports, you must first create report options. Each report can have several different options so that you can easily print the information you need. For example, you can create one report option to show summary information, and another option to show detailed information.



A single report option can't be used by multiple reports. For identical options for several reports, you must create them separately.

Use the Fixed Asset Management report options windows to create sorting, restriction and printing options for the reports that have been included with Fixed Asset Management.

To create report options:

1. Open one of the asset reports windows.
(Reports >> Fixed Assets >> Activity)
(Reports >> Fixed Assets >> Comparison)
(Reports >> Fixed Assets >> Depreciation)
(Reports >> Fixed Assets >> Inventory)
(Reports >> Fixed Assets >> Projection)
(Reports >> Fixed Assets >> Transaction)

2. Select a report from the Reports list.



For report options window information choose Help >> Index; then enter the name of the specific report options window.

3. Choose New to open the report options window. Your selection in step 2 determines which report options window appears.

4. Name the option and enter information to define the option. The name you choose for the option won't appear on the report. The selections available for defining report options vary, depending on the report type you've selected.
5. Enter range restrictions. The Ranges list shows the ranges available for each report. The available ranges vary, depending on the type of report.



You can enter only one restriction for each restriction type. For instance, you can insert one asset ID restriction or one document number restriction.

6. Choose Insert to add the range to the Restrictions List. To remove an existing range from the list, select the range and choose Remove.
7. Choose Email Options to enter email options for the report option. Once the email options are set up, you'll be able to send the reports in an email message from this window by choosing Email. You can also send this report in an email from any list view where the report option is displayed.
8. Choose Destination to select a printing destination. Reports can be printed to the screen, to the printer, to a file, or to any combination of these options. If you select Ask Each Time, you can select printing options each time you print this report option.

For more information about printing reports, see [Printing a report with an option](#) on page 148.

9. To print the report option from the report options window, choose Print before saving it. To print the report later, choose Save and close the window. The report window will be redisplayed.

Printing a report with an option

Use an asset report window to print a fixed assets report for which a report option has been set up.

To print a report with an option:

1. Open one of the asset reports window.
(Reports >> Fixed Assets >> Activity)
(Reports >> Fixed Assets >> Comparison)
(Reports >> Fixed Assets >> Depreciation)
(Reports >> Fixed Assets >> Inventory)
(Reports >> Fixed Assets >> Projection)
(Reports >> Fixed Assets >> Transaction)
2. Select a report from the Reports list.
3. Select a report option and choose Insert to insert the report option in the Email or Print List.
4. Choose Print to print the report options in the Email or Print List.

Customizing a report

Most of the existing reports in Fixed Asset Management can be modified to meet your needs. You can add or delete fields, change sorting options, add subtotals, or

you can customize reports using Report Writer. The following procedure describes the simplest method to customize a default report and set access to it. Refer to the Report Writer documentation for detailed instructions about using Report Writer.

To customize a report:

1. Print the report to the screen.
2. While the report is on the screen, choose Microsoft Dynamics GP menu >> Tools >> Customize >> Modify Current Report.

The Report Layout window will appear with the current report open.

3. In the Report Layout window, make any necessary changes to the appearance of the report.
4. Choose Windows >> Report Definition.
5. In the Report Definition window, change the sorting options, modify the report layout, or add report restrictions.
6. Choose OK to save the changes to the report.
7. Choose File >> Microsoft Dynamics GP to return to Fixed Asset Management.
8. Choose Microsoft Dynamics GP menu >> Tools >> Setup >> System >> Security and select the user, company and product to grant access for.
9. In the Type field, select Modified Reports.
10. In the Access List, double-click the name of the report you modified. An asterisk (*) appears, indicating that the selected user has access to the report.
11. Choose OK to save the changes to the user's security settings.

Fixed Asset Management Microsoft SQL[®] Server Reporting Services reports

You can view Fixed Asset Management Reporting Services reports from the Reporting Services Reports list. If you are using Reporting Services 2008, financial metrics for your home page also appear in the Reporting Services Reports list. You can access the Reporting Services Reports list from the navigation pane or from an area page in the Microsoft Dynamics GP application window. This report list appears if you specified the location of your Reporting Services reports using the Reporting Tools Setup window. See your System Setup Guide (Help >> Contents >> select Setting up the System) for more information.

The following Reporting Services reports are available for Fixed Asset Management.

Additions Report	Fixed Assets to General Ledger Reconciliation Report
Fixed Assets Depreciation Detail	Period Projection Report
Fixed Assets Depreciation Ledger	Retirements Report

To print a Fixed Asset Management Reporting Services report:

1. In the navigation pane, choose the Financial button, and then choose the Reporting Services Reports list.
2. Mark the Purchase Order Processing report that you want to print.
3. In the Actions group, choose View to open the Report Viewer.
4. In the Report Viewer, select the specifications for the report and choose View Report.
5. After viewing the report, select a format and print the report.

Glossary

Account

The type of record—asset, liability, revenue, expense, or owner’s equity—traditionally used for recording individual transactions in an accounting system. Also, the identifying alphanumeric characters that have been assigned to the record.

ACRS (Accelerated Cost Recovery System) tables

Tables to calculate depreciation for personal property, real estate, real estate using modified straight-line, low income housing, and foreign real property. Created by the Economic Recovery Tax Act of 1981 for US tax purposes. Depreciation can be calculated for assets acquired from 1981 through 1986.

Amortization

The gradual reduction of a liability in regular payments over a specified period of time. These payments must be enough to cover both principal and interest. Also, writing off an intangible asset investment over the projected life of the assets.

Asset

An item of value owned by an individual or corporation, especially that which could be converted to cash. On a balance sheet, assets are equal to the sum of liabilities, common stock, preferred stock, and retained earnings.

Asset book

Accounting records—ledgers or journals—for a specific reporting purpose, such as financial or tax. All assets to be included for the reporting purpose would be included in the asset book.

Asset group

A collection of assets with a similar characteristic.

Averaging convention

Rules for calculating depreciation in the year of the acquisition of the asset and the year of the disposal of the asset.

Book

See [Asset book](#).

Capitalize

To classify the cost of an asset as a long-term investment, rather than charging it to current operations.

Clearing account

An asset account that is debited in Purchasing Order Processing or Payables Management for the PURCH type distribution line in the Purchasing Distribution Entry window. This account is credited when an asset is added. At the end of each period, if the balance in the clearing account is zero, items in Purchasing Order Processing or Payables Management that need to be capitalized are added in Fixed Asset Management.

Corporate book

The accounting records for financial reporting purposes, based on the applicable accounting principles. See also [Tax book](#).

Cost basis

The purchase price of an asset, including freight, tax, and other expenses, less any adjustments, such as Section 179 Expense Deduction and salvage value. Used to determine capital gains and capital losses for tax purposes.

Depreciation

The allocation of the cost of an asset over a period of time for accounting and tax purposes. Also, a decline in the value of an asset due to general wear and tear or obsolescence.

Depreciation-sensitive

Changes that affect depreciation. When a value in a depreciation-sensitive field is changed, depreciation must be recalculated for that asset.

Expense

A cost incurred by a business in an attempt to obtain revenue.

Filter

An option to restrict specific information.

Fiscal period

Divisions of the fiscal year, usually monthly, quarterly, or semiannually, when transaction information is summarized and financial statements are prepared.

Fiscal year

An accounting period of 365 days—366 days in leap years—but not necessarily starting on January 1.

Inflation

The overall price movement—generally upward—of goods and services in an economy.

Insurance year

The year reproduction cost of an asset is based on.

Investment Tax Credit (ITC)

An investment tax credit (ITC) taken for US tax purposes for the purchase of specific types of business property. The credit must be taken in the year of purchase and is limited by a maximum amount. The ITC was eliminated by the Tax Reform Act of 1986.

Luxury auto

A limit on the annual recovery allowances—depreciation—that can be taken for US tax purposes.

Master asset ID

An ID used to group components of a single asset or related assets. For example, a computer might be considered an asset that contains a CPU, a monitor, and a printer as components. You can assign the same master asset ID to each component so that the parts are related and can be tracked together.

Net cost basis

The Original Cost Basis, minus Section 179 Expense Deduction, minus ITC Cost Reduction Amount, plus or minus Miscellaneous Cost Adjustment.

Physical location

The actual place where an asset is located; for example, a building, a floor in a building, or a room in a building.

Prior period adjustment

An adjustment for an error that was not discovered during the period in which it occurred.

Prior year depreciation

Depreciation that relates to years earlier than the current fiscal year.

Proceeds

The value—in cash or anything not in the form of cash—received for an asset.

Projected depreciation

The forecasted allocation of the cost of an asset over a period of time for accounting and tax purposes.

Purchasing transaction

A transaction that originated in Payables Management or Purchase Order Processing.

Recalculate option

Calculates a new rate of depreciation using the new cost basis data, but does not make adjusting entries for depreciation already taken. The new rate of depreciation will be used the next time the depreciation routine is completed.

Receiving

Recording the receipt of assets that have been ordered from a vendor via a purchase order. Receiving also refers to the recording of the invoice for the assets received.

Reset Life option

Recalculates depreciation from the date it was placed in service forward to the date the asset has already been depreciated. If there are adjustments to the depreciation for any period, they will be written to the financial detail table.

Reset Year option

Recalculates depreciation from the beginning of the year forward to the date the asset has already been depreciated. If there are adjustments to the depreciation for any period, they will be written to the financial detail table.

Retire

To sell or dispose of a fixed asset, including destroying or abandoning the asset. A retired asset is no longer producing revenue.

Section 179 Expense Deduction

US Tax Section 179 allows expensing all or a portion of the cost of an asset in the year of acquisition, rather than expensing, or depreciating, over the life of the asset. Any portion of the cost of an asset taken as Section 179 cannot be taken also as depreciation. For more information about additional restrictions and rules, contact a tax professional.

Special depreciation allowance

An additional first-year depreciation deduction. If used with the Job Creation and Worker Assistance Act of 2002, the deduction is equal to 30 percent of the adjusted basis of qualified property. For more information, contact a tax professional.

Spread

Options that account for the allocation of proceeds and expenses of sale for selected assets when mass retiring those assets.

Suffix

Number used to distinguish multiple assets with the same asset ID. Might be used to identify components of assets or assets that have been partially retired or transferred.

Switchover

Option that changes the depreciation method of an asset when the depreciation for an asset is greater using the switchover method than the current depreciation method. The depreciation method automatically will change to the switchover method. Switchover will only occur at the beginning of the year when the yearly depreciation rate is calculated for the next year.

Tax book

The accounting records for tax reporting purposes, based on the applicable tax laws. *See also* [Corporate book](#).

TEFRA

The Tax Equity and Fiscal Responsibility Act of 1982 produces additional revenue through a combination of federal spending cuts, tax increases, and reform measures for US tax purposes.

Transfer

The movement of an asset to a new general ledger account, property tax location, physical location, structure, or master asset ID. Typically affects the future allocation of depreciation expense for the asset.

Vendor

A person or company providing goods and services in return for payment.

Year-end closing

A process used to zero out year-to-date values and update beginning of year values for assets, including quantities, depreciation, and maintenance.

Index

A

- Account Group Setup window
 - creating account groups 28
 - displaying 29
- account groups
 - creating 28
 - overview 27-28
- account records, creating 42
- amortization codes, calculations 19
- Asset Account window
 - creating asset account records 42
 - displaying 42
- Asset Book Inquiry window
 - displaying 135
 - viewing book information 135
- Asset Book ITC Inquiry window, displaying 135
- asset book ITC records, creating 46
- Asset Book ITC window
 - creating asset book ITC records 46
 - displaying 46
- asset book records
 - creating 43
 - creating for existing assets 65
 - deleting 82
 - depreciating 96
 - field information 68
 - importing 65
 - projecting depreciation 98
 - recalculating depreciation 97
 - reversing depreciation 97
 - viewing information 135
- Asset Book window
 - creating asset book records 43
 - deleting asset book records 82
 - displaying 43
- asset class IDs, account groups 42
- asset class records, creating 16
- Asset Delete Utility window
 - deleting asset records 118
 - displaying 118
- asset fields
 - transferred from Payables Management 52
 - transferred from Purchase Order Processing 59
- Asset Financial Detail Summarize window
 - displaying 105
 - summarizing financial data 105
- asset general information, field information 66
- Asset General Information window
 - changing asset information 79
 - creating asset records 39
 - displaying 40
- Asset Group Search window, displaying 76

- asset groups
 - building 76
 - creating 77
 - deleting 78
 - importing data 77
 - removing asset records 78
 - searching for asset records 75
 - selecting asset records 75
 - viewing asset records 77
- Asset Import/Export window
 - creating book records 65
 - displaying 65
 - importing asset records 65
 - importing physical location IDs 111
- Asset Inquiry window
 - displaying 134
 - viewing asset information 133
- asset insurance
 - creating records 47
 - field information 69
- Asset Insurance window
 - creating insurance records 47
 - displaying 47
- asset lease
 - creating records 48
 - field information 69
- Asset Lease window
 - creating lease records 48
 - displaying 48
- Asset Purchase window, displaying 41
- Asset Purge window
 - deleting asset data 105
 - displaying 105
- asset records
 - adding 57
 - adding from other modules 42
 - adding from Purchase Order Processing by Account option 56
 - adding from Purchase Order Processing by Receipt line option 58
 - by Account line option 56
 - by Receipt line option 58
 - changing 79
 - changing for groups 82
 - creating account records 42
 - creating insurance records 47
 - creating lease records 48
 - creating user data records 48
 - deleting 118
 - deleting information 105
 - depreciating 95
 - field mappings 66
 - general information 39
 - guidelines for importing data 63
 - importing 65
 - partial transfer options 86
 - partially retiring 91
 - partially transferring 86
 - projecting depreciation for assets in one or more books 98

- asset records (*continued*)
 - projecting depreciation for one asset 98
 - reconciling 117
 - recording the disposal 90
 - recording the retirement 94
 - recording the sale of a group of assets 94
 - recording the sale of an asset 90
 - Require Account option 109
 - retirement options 89
 - retiring 90
 - reversing retired records 92
 - searching for asset records 75
 - transferring 85
 - transferring multiple assets 87
 - transferring Payables Management information to asset records 52
 - updating labels 117
 - viewing in groups 77
 - viewing information 133
- asset retirement, options 89
- asset retirement records, viewing information 138
- asset spreads, options 92
- asset suffix, description 39
- asset user data, field information 70
- Asset User Data window
 - creating user data records 48
 - displaying 49
- Asset Year End window
 - displaying 104
 - processing year-end activities 104
- averaging conventions
 - list 19
 - overview 19

B

- batches, rebuilding integrated 109
- book class records, creating 21
- Book Class Setup window
 - creating book class records 21
 - displaying 21
- Book Compare Inquiry window
 - displaying 136
 - viewing multiple book information 136
- book records
 - comparing book information 136
 - creating 15
 - creating class records 21
- Book Setup window
 - creating book records 15
 - displaying 15
- Build Fixed Assets Fiscal Calendar window
 - building the fiscal calendar table 12
 - displaying 12
 - rebuilding the fiscal calendar table 12
 - synchronizing quarter records 14
 - verifying fiscal calendar years 13

- C**
 Capital Item option, adding assets 58
 changes since last release, information about 4
 class IDs, account groups 42
 class records, creating 16
 Class Setup window
 creating class records 16
 displaying 16
 company records, setting up 23
 cost basis, adjusting to equal the net cost basis 47
 Create Group window, entering new group names 113
 current upgrade information, accessing on the Web 4
- D**
 Default Accounts window, displaying 25
 Depreciate Asset window
 depreciating asset records 95
 displaying 95
 projecting depreciation 98
 recalculating depreciation 97
 reversing depreciation 97
 depreciation
 adjusting the cost basis 47
 calculating mid-quarter 83
 calculations 17
 depreciation-sensitive fields 80
 methods 17
 options 47
 recalculating 80
 Depreciation Process Information window
 depreciating assets in multiple books 96
 displaying 96
 depreciation projection information, viewing 140
 Depreciation Projection window
 displaying 98
 projecting depreciation 98
 destinations, default report destinations 146
 documentation, symbols and conventions 3
- E**
 error log, viewing 139
 Error Log Inquiry window
 displaying 139
 viewing the error log 139
 Expand Location window, entering information 41
 Expand Manufacturer Name window, entering information 41
 Expand Transfer window, entering new account numbers 85
 Expand User Fields window
 defining user-defined fields 26
 displaying 35
 Expand User Fields window (*continued*)
 setting up user-defined field values 35
- F**
 FA Error Log Listing report, printing 139
 FA PO Additional Information window
 adding asset records 57
 displaying 58
 transferring information 59
 FA Purchasing Trxs Purge window
 deleting purchase transactions data 119
 displaying 119
 field values, list 71
 file formats, reports 146
 financial data
 summarizing 105
 viewing 137
 financial detail activity
 abbreviations 121
 adding records 122
 changing records 122
 deleting records 125
 depreciating records 125
 descriptions 121
 mass changes to records 124
 mass retiring records 128
 mass transfer of records 127
 retiring records 127
 transferring records 126
 unretiring records 129
 Financial Detail Display window
 displaying 138
 viewing financial information 137
 Financial Detail Inquiry window, displaying 135
 Financial Detail Maintenance window, viewing distribution transaction information 44
 fiscal calendar
 building 12
 rebuilding 12
 verifying 13
 fiscal period
 setting up quarters 13
 synchronizing quarters 14
 Fiscal Period Inquiry window, displaying 13
 Fixed Asset Purchasing Transactions window, transferring Payables Management information to asset records 53
 Fixed Asset User Preferences window, setting up user preferences 34
 Fixed Assets Company Setup window
 company options 23
 displaying 25
 purchasing integration options 24
 setting up company records 25
 transaction data 24
 Fixed Assets General Ledger Posting window
 displaying 107
 migrating from another system 107
 updating General Ledger 108
 Fixed Assets Mass Change window
 changing information for asset groups 82
 displaying 82
 Fixed Assets Mass Retirement window
 displaying 94
 recording the retirement of assets 94
 recording the sale of assets 94
 Fixed Assets Mass Transfer window
 displaying 87
 transferring multiple assets 87
 Fixed Assets Purchasing Posting Account Setup window, entering Fixed Assets posting accounts 29
 Fixed Assets Purchasing Posting Accounts Setup window, displaying 30
 Fixed Assets Purchasing Transactions Display window
 displaying 141
 viewing transaction information 141
 Fixed Assets Purchasing Transactions window
 displaying 53
 transferring Purchase Order Processing information to asset records 56
 viewing purchasing transactions information 141
 Fixed Assets Reconcile window
 displaying 110
 rebuilding integrated batches 109
 reconciling asset information 117
 Fixed Assets User Preferences window, displaying 34
- G**
 gain/loss projections, calculations 89
- H**
 help, displaying 3
 Help menu, described 3
- I**
 icons, used in manual 3
 Import Group window, displaying 77
 insurance, asset field information 69
 insurance class records, setting up 30
 insurance records
 creating 47
 importing 65
 Insurance Setup window
 displaying 30
 setting up insurance class records 30
 integrated batches, rebuilding 109
 integration
 General Ledger 9
 Payables Management 9

- integration (*continued*)
 - Purchase Order Processing 9
 - with Multicurrency Management 61
 - with Payables Management 51
 - with Purchase Order Processing by Account option 55
 - with Purchase Order Processing by Receipt Line option 58
- investment tax credit (ITC), adding asset book ITC records 46
- L**
 - lease company records, creating 31
 - Lease Company Setup window
 - creating lease company records 31
 - displaying 31
 - lease records
 - creating 48
 - importing 65
 - location records, creating 31
 - Location Setup window
 - creating location records 31
 - displaying 32
 - lookup window, displaying 4
 - loss/gain projections, calculations 89
 - luxury automobile
 - limits for assets 44
 - tax limits 95
- M**
 - Mass Change window, calculating
 - mid-quarter depreciation 83
 - misplaced assets, reconciling 113
 - Misplaced Physical Inventory window,
 - viewing inventory 113
 - missing assets, reconciling 113
 - Missing Physical Inventory window,
 - viewing inventory 113
- N**
 - navigation, symbols used for 3
 - net cost basis
 - adjusting the cost basis 47
 - calculation 46
 - new features, information about 4
- P**
 - partial retirement, options 91
 - partial transfer, options 86
 - Physical Inventory window
 - displaying 113
 - reconciling assets 113
 - reconciling the physical location 113
 - physical location records
 - creating 32
 - reconciling 112
 - Physical Location Setup window
 - creating physical location records 32
 - displaying 32
 - posting accounts, entering 29
 - process server, activities 147
- Projections Inquiry window
 - displaying 140
 - viewing depreciation projection information 140
- purchasing transactions
 - deleting 119
 - using in Fixed Asset Management 24
 - viewing 141
- Purchasing Zoom window, viewing
 - purchasing information 141
- Q**
 - Quarter Setup window
 - displaying 14
 - setting up quarter records 13
 - quarters
 - setting up 13
 - synchronizing 14
- R**
 - report options
 - creating 147
 - printing 148
 - report security, for modified reports 148
 - Report Writer, described 148
 - Reporting Services reports
 - printing 149
 - reports 149
 - reports
 - file formats 146
 - mailing with MAPI 146
 - printing, default destinations 146
 - printing to a file 146
 - printing to a printer 146
 - printing to the screen 146
 - Reporting Services reports 149
 - restricting 147
 - samples of customized reports 143
 - samples of reports 143
 - samples with technical names 143
 - sorting 147
 - required fields, described 4
 - Reset Asset ID window, displaying 80
 - resources, documentation 3
 - retirement
 - partial 91
 - recording for a group of assets 94
 - reversing 92
 - retirement codes, creating 33
 - Retirement Display window
 - displaying 138
 - viewing asset retirement information 138
 - Retirement Maintenance window
 - displaying 90
 - partially retiring asset records 91
 - recording the disposal of asset records 90
 - recording the sale of asset records 90
 - Retirement Setup window
 - creating retirement codes 33
- Retirement Setup window (*continued*)
 - displaying 33
- Retirement Undo window
 - displaying 92
 - reversing retired asset records 92
- S**
 - Section 179 Expense Deduction 45
 - Select Assets window
 - building asset groups 76
 - deleting asset groups 78
 - displaying 76
 - importing data to create asset groups 77
 - removing asset records 78
 - viewing asset records in groups 77
 - special depreciation allowance
 - calculation 17
 - yearly limit 17
 - structure IDs, creating 33
 - Structure Setup window
 - creating structure IDs 33
 - displaying 33
 - symbols, used in manual 3
- T**
 - tables, used by specific reports 143
 - technical names, reports 143
 - transactions, updating General Ledger 108
 - Transfer Display window
 - displaying 140
 - viewing transfer information 139
 - transfer information, viewing 139
 - Transfer Maintenance window
 - displaying 85
 - partially transferring asset records 86
 - transferring asset record information 85
- U**
 - upgrade information, accessing on the Web 4
 - user data, creating records 48
 - User Fields List Setup window
 - defining default values 26
 - displaying 35
 - setting up user-defined field values 35
 - user preferences
 - list 34
 - setting up 34
 - user-defined
 - creating records 48
 - importing records 65
- W**
 - what's new, accessing 4
- Y**
 - year-end, processing activities 104

